

FUJITSU Software BS2000 ASTI

Version V2.0F June 2016

Readme file

All rights reserved, including intellectual property rights. Technical data subject to modifications and delivery subject to availability. Any liability that the data and illustrations are complete, actual or correct is excluded. Designations may be trademarks and/or copyrights of the respective manufacturer, the use of which by third parties for their own purposes may infringe the rights of such owner.

Copyright © 2016 Fujitsu Technology Solutions GmbH

Fujitsu and the Fujitsu logo are trademarks or registered trademarks of Fujitsu Limited in Japan and other countries. BS2000 is a trademark of Fujitsu Technology Solutions GmbH in Germany and other countries.

4
5
5
5
5
9
9
10
11
11
12
12
13
14
14
15
15
15
16

1 General

The subsystem ASTI is a component that manages the new "Service" interface and performs the communications between one or more client tasks and at least one service tasks.

ASTI is part of the basic configuration and is initially only released for internal purposes. Since the commands appear on the user interface they are described in this paper.

- *2 The release level is that of June 2016.
- *2 Changes to release level June 2014 are marked with *1.
- *1 Changes to release level July 2013 are marked with *2.

This and other current Readme files are shipped on the SoftBooks DVD and are available online at http://manuals.ts.fujitsu.com/.

2 Operating

ASTI is not a stand-alone system that directly provides a service to the customer. It is intended for subsystem developers that have to realize a type of client/server model. ASTI thereby provides the connection between the client and the server. Connections can be made in all directions (TU-TU, TPR-TU, TU-TPR and TPR-TPR). The client issues an order to the server and this is then processed by the server.

ASTI takes care of the communications between the different tasks.

ASTI takes the order and puts it into a wait queue for the service concerned. All parameters are stored. The service queries ASTI as to whether there is an order pending for it. If there is one for this service, it is forwarded to the service concerned. The service executes the function and reports the result to the client. The processes can be delivered either synchronously, i.e. the client waits for the result, or asynchronously. The client can also control how long the orders have to be held in the system before they are processed. An order is stored until it is processed. The client can also control how long the result of an order is stored.

There are three options:

- 1. The client does not want to receive a result; ASTI rejects the result.
- 2. The client wants to receive the result during the service session. The return message is held in main memory and deleted after the service session is ended.
- The client wants to receive the result in all cases. The return message is stored on the disk. The return message is only deleted after it has been successfully delivered.

The subsystem ASTI manages the orders of the services in the files \$TSOS.SYSQUE.ASTI and \$*. SYS.<tsn>.<service-name>.<order-id>.

The format of these files has changed and cannot be used as of ASTI V2.0B.

Therefore these files must be removed before migrate ASTI V2.0A to V2.0B.

Subsystem ASTI must not be created.

\$TSOS.SYSQUE.ASTI is created at start of the subsystem ASTI, if the file does not exist.

Following procedure is recommended:

STOP-MAIL-SERVICE

*1

STOP-LWRESD (as of BS2000/OSD-BC V9.0)

STOP-SUBSYSTEM REWAS (as of BS2000 OSD/BC V10.0 on SE Server)

STOP-SUBSYSTEM ASTI

DELETE-FILE \$TSOS.SYSQUE.ASTI

DELETE-FILE \$*. SYS.<tsn>.<service-name>.<order-id> (if existing)

3 Commands

3.1 Command Return Codes

All commands have SUBCODE1(), SUBCODE2() and MAINCODE() set. If II is OK, the MAINCODE has the value CMD0001. If an error occurs the MAINCODE contains the key of the error message and the SKIP function is triggered.

The service and the client commands also set SDF-P variables. These variables are only set in positive cases.

SVTVAR-ORDERID SVTVAR-SERVICE SVTVAR-DATA

3.2 Service Management

These commands are responsible for controlling the service concerned. The service can be started and stopped with them. It is also possible to output the status of the service and carry out a few modifications.

3.2.1 Command: START-SERVICE

This command starts a service. A service is a batch job that is generated by ASTI and starts just one program. The program is defined by a symbol and a library. When the program terminates, the job also terminates.

```
START-SERVICE
```

```
SERVICE-NAME = <text_4..16>
FROM-FILE = *LIBRARY-ELEMENT(..)
            (LIBRARY = <full-filename_1..54>
            ,SYMBOL = <composed-name_1..32_with_underscore>)
               | <c-string_1..32_with_lower-case>)
      | *BY-IMON(..)
            (LOGICAL-ID = SYSLNK | <composed-name_1..30>
            ,INSTALLATION-UNIT = <composed-name_1..30>
            ,VERSION = *STD | <version 3..7>
            ,DEFAULT-LIBRARY = <full-filename 1..54>
            ,SYMBOL = <composed-name 1..32 with underscore>)
      | *NONE(TSN = <text_4..4>)
      *PROCEDURE(..)
            (<full-filename_1..54> | *LIBRARY-ELEMENT(..))
               (LIBRARY = <full-filename 1..54>
               ,ELEMENT = <composed-name 1..32 with underscore>)
,PROCESSING-ADMISSION = *FROM-ORDER
             *FROM-START
            | *EXPLICIT(..)
               (USERID = <name_1..8>
               ACCOUNT = < text_1..8 > 
               ,PASSWORD = *NONE | < secure 1... 8>)
```

```
,ALLOWED-USER = *ALL
                    | *NONE
                    *START-USER-IDENTIFICATION(..)
*2
                          (ALTERNATE-ADMIN = *NONE | list_poss(8): <name_1..8>)
                    | *BY-GUARD(NAME = <full-filename_1..24>)
            ,ORDER-RECOVERY = *PARAMETER(..)
                       (ALLOWED = *NO | *SESSION-WIDE | *PERMANENT
                        ,DEFAULT = *NO | *SESSION-WIDE | *PERMANENT)
            ,ORDER-LIMIT = 255 | <integer_1..32000>
            ,NUMBER-OF-TASKS = \underline{1} | <integer_1..16>
                       (MINIMAL = 0 | < integer_0..16 >
                       ,MAXIMAL = 16 | <integer_1..16>)
            ,START-PARAMETER = *NONE | <c-string_1..1800> | <x-string_1..3600>
            ,NOT-ALLOWED-CMD = *NONE
                      | list-poss(5): *STOP-SERVICE | *MODIFY-SERVICE-PARAM |
                               *SEND-ORDER | *DELETE-ORDER |
                               *REQUEST-ORDER-RESULT
            ,NOT-ALLOWED-SVC = *NONE |
                      | list-poss(5): *SVTSTOP | *SVTMODI |
                               *SVTSORD | *SVTDORD | *SVTRORD
            ,SYSTEM-OUTPUT = *ALL | *NONE | *STDOUT | *PARAMETER(..)
                     (SYSLST-OUTPUT = *STDOUT | *NONE | *PRINTER | *MAIL
                     ,SYSOUT-OUTPUT = <u>*STDOUT</u> | *NONE | *PRINTER | *MAIL )
*2
            ,MONJV = *NONE | <full-filename_1..24>
                                   a name that is unique for this system.
            SERVICE-NAME
                                   Services beginning with $ can only started by TSOS
            FROM-FILE
                                   this parameter supplies the load library and the symbol
                                   to be loaded. Either direct input *LIBRARY-ELEMENTor
                                   indirect input via the installation monitor *BY-IMON are
                                   possible. The option *NONE can be used to make a run-
                                   ning dialog task be seen as a service task.
            *LIBRARY-ELEMENT
             LIBRARY
                                   name of a module library.
                                   name of a CSECT or an ENTRY with which a module is
             SYMBOL
                                   loaded and started.
            *BY-IMON
             LOGICAL-ID
                                   logical name of the module library.
             INSTALL-UNIT
                                   name of a product
                                   version of a product.
             VERSION
                                   *STD is the highest installed version.
                                   default library name, if the product is not installed.
             DEFAULT-LIB
                                   name of a CSECT or an ENTRY with which a module is
             SYMBOL
                                   loaded and started
            *NONE
```

a TSN of a dialog task can be input here

TSN

*PROCEDURE

FILENAME Name of a procedure file
LIBRARY Name of a module library.
ELEMENT Name of J-element in a library

PROCESSING-ADMISSION regulates which user environment the service works

in.

*FROM-ORDER the service takes over the user environment of the task

that sent the order. This function is not allowed for

FROM-FILE=*NONE.

*FROM-START the service contains a user ID that is not changed during

operation.

*EXPLICIT Start User-ID of the service

USERID <text_1..8> the specified user ID is taken. ACCOUNT <text_1..8> account number of the user ID.

PASSWORD *NONE no password assigned.

<secure1..8> password of the user ID.

ALLOWED-USER controls access to the service.

*START-USER-IDENTIFICATION() only the same user ID as with

START-SERVICE is allowed, or one of the alternate us-

er ID's from the list.

*2 ALTERNATE-ADMIN a list of up to 8 (different) user ID's which also can man-

age the service

*BY-GUARD the user IDs are permitted via a guard.

The guard is in the start user ID.

The length of the guard is (1..8 Char).

*NONE the service uses only the service management.

*ALL all tasks have access.

ORDER-RECOVERY the value range of the ORDER-RECOVERY parameter

in the SEND-ORDER command can be influenced with

this parameter.

ALLOWED the value range of the ORDER-RECOVERY parameter

in the SEND-ORDER command can be limited with this

parameter.

*NO the ORDER and the RESULT are only held in main

memory. If a task or the service dies, the orders concerned are acknowledged negatively. If the order

task is missing, the results are deleted.

*SESSION-WIDE the ORDER is held in memory until the order has been

processed. Unprocessed orders and results are held in main memory and only deleted after SESSION-END

(/SHUTDOWN or /STOP-SUB ASTI).

*PERMANENT the ORDER and the RESULT are stored on the disk.

Each part is only deleted after the respective action is completed. With this function, incorrect programming can create order cadavers that remain in the order user

ID in the form of files.

DEFAULT the ORDER-RECOVERY default value is set with this

parameter.

ORDER-LIMIT this defines the maximum number of ORDERS being

processed in one time.

NUMBER-OF-TASKS 1-16

number of service tasks that work for this service.

*MINIMAL 0-16 the minimal number of service tasks,

which would be changed by

/MODIFY-SERVICE-PARAMETER.

*MAXIMAL 1-16 the maximal number of service tasks,

which would be changed by

/MODIFY-SERVICE-PARAMETER.

START-PARAM this parameter must be queried by the service after the

service task is started. The record is used for initializing

the service.

NOT-ALLOWED-CMD specific commands can be blocked for a service with this

parameter.

*STOP-SERVICE This service cannot be stopped with this com-

mand.

*MODIFY-SERVICE-PARAM this service cannot be modified.
*SEND-ORDER no order can be placed to this service.

*DELETE-ORDER no orders can be deleted. *REQUEST-ORDER-RESULT no results can be fetched.

NOT-ALLOWED-SVC program calls for a service can be blocked with this

parameter.

*SVTSTOP this service cannot be stopped by the program.
*SVTMODI this service cannot be modified by the program.
*SVTSORD no orders can be placed by the program.
*SVTDORD no orders can be deleted by the program.
*SVTRORD no results can be fetched by the program.

Note: The TPR interface is not subject to any of these restrictions

SYSTEM-OUTPUT setting parameter of EXIT-JOB

*ALL SYSLST and SYSOUT are printed

*NONE no output

*STDOUT Behavior specified by CLASS-II-Option "SSMOUT"

*PARAMETER

SYSLST-OUTPUT Parameter for SYSLST SYSOUT-OUTPUT Parameter for SYSOUT *STDOUT Class II Option "SSMOUT" *NONE no output of selected file *PRINTER print of selected file *MAIL sending file as mail

*2 MONJV The name of a JV to monitor the task.

*2

*NONE MONJV is not used here

Note: there can be only one task being monitored by a MONJV.

Command: STOP-SERVICE 3.2.2

This command stops a service. The service is set to termination mode. The separate tasks must stop themselves. New orders are no longer accepted.

Existing order are handled according to the save order value

STOP-SERVICE SERVICE-NAME= <text 4..16> Name of service

Command: SHOW-SERVICE-STATUS 3.2.3

The status of a single service or of all services are displayed with this command. This information can also be shown into OPS-variables.

SHOW-SERVICE-STATUS SERVICE-NAME = *ALL | <text_4..16>

Output SERVICE-NAME=*ALL

CID	CEDVICE NAME	LICEDID	CTATUC	TACK ALLOWED LICES	
SID	SERVICE-NAME	USERID	STATUS	TASK ALLOWED-USEF	R PRO-ADM
@006	SERVICE3	ASTITEST	RUNNING	0001 ALL	FROM-START
@005	SERVICE2	TSOS	RUNNING	0001 START-USERID	FROM-ORDER
@004	SERVICE1	TSOS	RUNNING	0001 ALL	FROM-ORDER
@003	MAILCLNT	TSOS	RUNNING	0001 ALL	FROM-START
@002	LWRESD	TSOS	RUNNING	0001 START-USERID	FROM-START
@001	\$ASTIQUE	TSOS	RUNNING	0001 ALL	FROM-START

Output SERVICE-NAME=MAILCLNT

SID SERVICE-NAME STATUS ADMINSTR ALLOWED-USER PROCESSING MODE @003 MAILCLNT RUNNING FROM-START SERVICE TSOS ALL

ORDER-RECOVERY: ALLOWED = PERMANENT DEFAULT = PERMANENT

LIMITS (MIN=00,MAX=16) SERVICE-TASKS: 01 SYSOUT = *NONE SYSTEM-OUTPUT: SYSLST = *NONF **MSSRVC** SYMBOL

LIBRARY

:SQN6:\$TSOS.SYSLNK.MAIL.032.BACKEND *NONE GUARD

TASK: 9UKX ACT-ORDER: 000 TERMINATION: NONE START-PARAM: NONE

% SVTS000 Service MAILCLNT: Command executed

3.2.4 Command: MODIFY-SERVICE-PARAMETER

MODIFY-SERVICE-PARAMETER

SERVICE-NAME = <text_4..16>

,ALLOWED-USER = *UNCHANGED

| *ALL

| *START-USER-IDENTIFICATION

| *BY-GUARD(NAME=<full-filename_1..24>)

,NUMBER-OF-TASKS = *UNCHANGED | *PAST-VALUE | <integer_0..16>

,ORDER-LIMIT = *UNCHANGED | <integer_1..32000>

,START-PARAMETER = *UNCHANGED | *NONE

| <c-string_1..1800> | <x-string_1..3600>

SERVICE-NAME Name of service

ALLOWED-USER controls who can use the service

NUMBER-OF-TASKS

0-16 number of service tasks that can work with the

same SERVICE name. The number of tasks can be reduced to 0. In this case, the service is still present and accepts orders, but does not execute them. This parameter is ignored with a

dialog service.

*PAST-VALUE sets the number to the value before the last

/MODIFY-SERVICE-PARAMETER

ORDER-LIMIT the number of orders for this service that are in

the system can be limited with this parameter.

START-PARAMETER the initialization parameters can be changed with

this parameter. The next PROCESS-ORDER

receives the RC: "new parameter". If a PROCESS-ORDER is in the wait queue when

this parameter is modified, RC: 00040010 is

only set after the queue timeout.

3.3 Client Commands

These commands connect the client to the service.

3.3.1 Command: SHOW-ORDER-STATUS

Information about orders is output with this command. The command works asynchronously to normal operation and consistency between the number of orders and the separate sub-queues is therefore not assured. This information can also be shown into OPS-variables

This information can also be chewn into

SHOW-ORDER-STATUS

*ALL (ORDER-ID = < x-text_1..16 >)

INFORMATION:

*SUMMARY number of orders per subqeue

*ORDER-LIST all relevant order IDs, including status

*ALL Informationen about the orders

(administrator about all orders, normal user about his

own)

SERVICE-NAME name of the service

ORDER-ID order identification

during the same subsystem session the last 8 bytes are sufficient, for orders of other sessions all 16 bytes

are required.

Output information *SUMMARY

SERVICE ALL-Q RDY-Q ACT-Q RES-Q WAI-Q NRR-Q IAC-Q DEQ-R

SERVICE4 3 1 1 1 0 0 0 0

ALL-Q all orders of this service

RDY-Q all orders that are waiting for execution by the service

ACT-Q all orders that are currently being executed RES-Q all results that have not been fetched yet WAI-Q all orders that have been deferred NRR-Q all results that have not been requested

AC-Q orders from stopped service (session-wide)

DEQ-R results whose tasks no longer exist

Output information *ORDER-LIST

 ORDER-ID
 SERVICE
 QUEUE
 TASK

 1266CAAA00000007 SERVICE4
 READY-QUEUE
 0BA4

 1266CAAA00000006 SERVICE4
 ACTIVE-QUEUE
 0BA4

 1266CAAA00000005 SERVICE4
 RESULT-QUEUE
 0BA4

% SVTS000 Service SERVICE4: Command executed

Output information *ALL

ORDER SERVICE CURRENT QUEUE 1266CAAA00000007 SERVICE4 READY-QUEUE USERID ACCOUNT TSN USER-STATE

TSOS ADMINSTR 0BA4 RESULT-REQUESTED

Comment:

USERID User Id of the sender account of the senders TSN TSN of the sendertask USER-STATE state of result request

3.3.2 Command: DELETE-ORDER

Either one order or all orders of a service can be deleted with this command. With a normal user, only orders with his user ID are deleted and with the administrator, all orders of the service concerned.

DELETE-ORDER

```
ORDER-ID = *TASK(SERVICE-NAME = <text_4..16>)
|*USER(SERVICE-NAME = <text_4..16>)
|*ALL(SERVICE-NAME = <text_4..16>)
|<x-text_1..16>
```

ORDER-ID order identification

during the same subsystem session the last 8 bytes are sufficient, for orders of other sessions all 16 bytes

are required.

Only orders from the same task are deleted

Exception: permanent orders, whose callers no longer exist.

*TASK(SERVICE-NAME=) all orders that this task sent to the service are

deleted, including permanent orders.

*USER(SERVICE-NAME=) all orders that were sent to the service by this

user ID are deleted, including permanent orders. all orders that were sent to the service by this

*ALL(SERVICE-NAME=) all orders that were sent to the service by this

user ID are deleted; with the administrator, all

orders are deleted.

Note:

All orders concerned are searched for and marked with "order to delete". Orders that are currently being processed by the service are completed by the service. If the client is waiting, the result is delivered. If the client is not waiting, the result is deleted. Orders in the ready queue or in the wait queue are deleted. If the client is waiting for the result, ASTI delivers a negative result (key: SVTS903).

3.3.3 Command: REQUEST-ORDER-RESULT

The result of an asynchronous order is fetched with this command. The result is thereby deleted in the ASTI management. Results of permanent orders whose caller task no longer exists can also be fetched with this command.

REQUEST-ORDER-RESULT

```
ORDER-ID= <x-text_1..16>

| *TASK(SERVICE-NAME=<text_1..16>)

| *USER(SERVICE-NAME=<text_1..16>)

,WAIT-FOR-RESULT = *YES (TIME-LIMIT= *NO

| <integer_15..65535>)

| *NO
```

ORDER-ID order identification

during the same subsystem session the last 8 bytes are sufficient, for orders of other sessions all 16 bytes

are required.

Only orders from the same task are deleted

Exception: permanent orders, whose callers no longer

exist.

*TASK the next order of this task is requested
*USER the next order of this user ID is requested

SERVICE-NAME selects the service

WAIT-FOR-RESULT specifies, if the client waits for the result.

The TIME-LIMIT specifies the time for waiting

With the *USER parameter, results whose task no longer exists can be fetched

3.3.4 Command: SEND-ORDER

An order is placed with this command.

SEND-ORDER

SERVICE-NAME = <text 4..16>

,WAIT-FOR-RESULT = $\underline{*YES}$ (TIME-LIMIT = *NO

| <integer_15..65535>)

| *NO (RESULT = <u>*NO</u> | *YES)

ORDER-RECOVERY = *STD

*NONE *SESSION-WIDE

| *PERMANENT ,DATA = *NO | <c-string 1...1800> | <x-string 1..3600>

SERVICE-NAME name of the service

WAIT-FOR-RESULT

*YES the order is accepted and the task waits until the order is

completed. The result is displayed

TIME-LIMIT restricts the waiting time.

*NO the order is accepted and processed asynchronously.

RESULT=*NO no result requested

RESULT=*YES a result is requested, that must be fetched later with

/REQUEST-ORDER-RESULT.

ORDER-RECOVERY

*STD the default value of /START-SERVICE is taken.

*NONE no special measures are met regarding transaction

security.

*SESSION-WIDE the order is retained until acknowledged by the service

and the result is also retained until delivery to the client. If these events do not occur, the order or the result is

deleted when the session ends.

*PERMANENT in contrast to *SESSION-WIDE, neither orders nor result

are deleted at termination of the service or the

subsystem ASTI.

Results can be fetched at next start of ASTI session, orders are delivered at start of the service concerned.

DATA the contents of the parameter represent the order

to the service task.

3.4 Service Command

3.4.1 Command: PROCESS-ORDER

The service fetches orders from ASTI and returns results with this command.

PROCESS-ORDER

```
ACTION= *GET-ORDER (WAIT-FOR-ORDER = *YES(TIME-LIMIT = *NO | <integer_15..65535>) | *NO
```

*SEND-ACK (ORDER-ID=<x-text_1..16> ,RETURN-DATA = *NONE

> | <c-string_1..1800> | <x-string_1..3600>)

*SEND-NAK (ORDER-ID = <x-text_1..16> ,RETURN-KEY = <text_7..7>) ,RETURN-DATA = *NONE

| <c-string_1..1800> | <x-string_1..3600>)

*SEND-RETRY(ORDER-ID = <x-text_1..16> ,WAIT-TIME = <integer_1..2000> ,RETURN-DATA = <u>*NONE</u>

> | <c-string_1..1800> | <x-string_1..3600>)

*GET-START-PARAMETER

*GET-ORDER request a new order.

WAIT-FOR-ORDER

*YES the service task waits until a new order arrives.

*NO the service task checks whether a new order is pending

and continues working immediately.

*SEND-ACK order with ORDER ID was executed correctly.

RETURN-DATA return parameter
*NONE no value is returned

*SEND-NAK order with ORDER ID was aborted with an error.

RETURN-KEY specifies the error RETURN-DATA return parameter *NONE no value is returned

*SEND-RETRY the order can temporarily not be executed.

WAIT-TIME = time in seconds. Order should be

restarted in n seconds. The wait time may extend up to

the queue timeout (30 seconds).

RETURN-DATA return parameter *NONE no value is returned

*GET-START-PARAMETER initialization parameters are queried after the

service start or after a request via RC.

.

4 Macros

There are also macros available for the interfaces.

5 Procedures

5.1 Reset of a central lock in ASTI

A deadlock situation occurs, if a task, which holds a lock on central data of ASTI, terminates abnormally, so that the lock is not released. As long as this lock is not released, ASTI doesn't accept new orders or perform existing orders.

As long as there is no collaboration between task termination processing and ASTI, this problem cannot be avoided. To remove the deadlock situation and to avoid the reboot of the system, an "unlock" procedure **SYSPRC.ASTI.020.RESET-LOCK** is delivered as of ASTI V2.0C.

The procedure requires the TSOS privilege. It should be called, when a deadlock situation is suspected. The procedure displays a corresponding message, but does not perform any modifications.

SYSPRC.ASTI.020.RESET-LOCK performs the following operations:

- Get the content of the lock area in the Asti central lock table
- Depending on the lock content one of the following messages is displayed
 - 1. No deadlock situation: X'00000000' or X'FFFFFFFF', nothing must be done returned message: "ACTIVE-Q NOT LOCKED AT THE MOMENT"
 - 2. With any other content the following messages are displayed: "ACTIVE-Q LOCKED BY TSN <TSN>"
 RESET LOCK FOR EXISTING TSN <tsn>? (Y/N) or
 RESET LOCK FOR UNKNOWN TSN <tsn>? (Y/N)
- If "Y" given, the program HELGA is called to reset the lock.

5.2 Example of a Service procedure

```
/SET-PROCEDURE-OPTION
/BEGIN-PARAMETER-DECLARATION
/END-PARAMETER-DECLARATION
/&* DO.SERVICE
/&* THIS PROCEDURE REALIZES A SERVICE
/ PROCESS-ORDER ACTION=*GET-ORDER(WAIT-FOR-ORDER=*YES)
/ IF-CMD-ERROR:END-IF
/ IF (MAINCODE() NE 'SVTS016')
/ IF-BLOCK-ERROR;END-IF
/ IMPORT-VARIABLE VARIABLE-NAME=SVTVAR-ORDERID
/ IMPORT-VARIABLE VARIABLE-NAME=SVTVAR-SERVICE
/ IMPORT-VARIABLE VARIABLE-NAME=SVTVAR-DATA
/LOOP: REPEAT
   SHOW-VARIABLE VARIABLE-NAME=SVTVAR-SERVICE
   IF (MAINCODE() EQ 'CMD0001')
    PROCESS-ORDER ACTION=*SEND-ACK,ORDER-ID=&(SVTVAR-
ORDERID), -
     RET-DATA = 'OKAY'
    IF-BLOCK-ERROR; END-IF
   ELSE-IF (MAINCODE() EQ 'SVTS011')
   PROCESS-ORDER ACTION=*GET-START-PARAMETER
   IF-BLOCK-ERROR; END-IF
   WRITE-TEXT TEXT='START-PAR: SVTVAR-DATA'
   ELSE-IF (MAINCODE() NE 'SVTS016')
   WRITE-TEXT TEXT='ERROR MAINCODE = &(MAINCODE())'
    EXIT-BLOCK BLOCK=LOOP
   END-IF
   PROCESS-ORDER ACTION=*GET-ORDER(WAIT-FOR-ORDER=*YES)
  IF-CMD-ERROR; END-IF
/ UNTIL (MAINCODE() EQ 'SVTS016')
/ END-IF
[/EXIT-PROC]
/&* must be replaced to avoid CMD2001 during task termination
/EXIT-JOB
```