

Fujitsu Technology Solutions

SBA-BS2 (BS2000/OSD) Version 6.2A April 2009

Release Notice

All rights reserved, including intellectual property rights. Technical data subject to modifications and delivery subject to availability. Any liability that the data and illustrations are complete, actual or correct is excluded. Designations may be trademarks and/or copyrights of the respective manufacturer, the use of which by third parties for their own purposes may infringe the rights of such owner. For further information see http://ts.fujitsu.com/terms_of_use.html

Copyright © Fujitsu Technology Solutions 2009

Release Notice SBA-BS2 V6.2A

1	General General		
	1.1	Ordering	2
	1.2	Delivery	3
	1.3	Documentation	3
2	Soft	ware extensions	4
3	Technical information		4
	3.1	Resource requirements	4
	3.2	Software configuration	4
	3.3	Product installation	4
	3.4	Product use	5
	3.5	Obsolete functions	5
	3.6	Incompatibilities	5
	3.7	Restrictions	5
	3.8	Procedure in the event of errors	6
4	Hard	ware support	6

1 General

The SNMP basic agent BS2000 (SBA-BS2) product

- enables the network, system and application management of BS2000/OSD systems *) from a SNMP-based management system,
- informs the user of the status of the BS2000 systems, its components and applications and of any problems that have occurred.
- provides the base for linking the BS2000/OSD systems to a system spanning control centre,
- allows the access to information of BS2000/OSD over browser (e.g. Netscape).

This release notice is a summary of the major extensions, dependencies and operating information with respect to SBA-BS2 V6.2A under BS2000.

This Release Notice is supplied as a file in uppercase/lowercase. Customers will receive an updated version of this file should any subsequent changes be made.

To print this file, use the following command /PRINT-DOCUMENT FROM-FILE= SYSFGM.SBA-BS2.062.E, - / DOC-FORM=*TEXT (LINE-SPACING=BY-EBCDIC-CONTR) (English version:).

This Release Notice is also available online under http://manuals.ts.fujitsu.com/mainframes.html

If one or more previous versions are skipped when this product version is used, the information from the Release Notices (and README files) of the previous versions must be noted.

1.1 Ordering

SBA-BS2 V6.2A can be ordered from your local distributors.

SBA-BS2 V6.2A is subject to the general terms and conditions of the agreement for purchasing, using and servicing software products.

 $^{^{\}star}$) BS2000/OSD (R) is a registered trademark of Fujitsu Technology Solutions

1.2 Delivery

SBA-BS2 V6.2A files are delivered via SOLIS.

Delivery components: Product description:

The following delivery items are required regardless of the HSI:

Elements for installation in UFS SINLIB.SBA-BS2.062 and executable agents SYSFGM.SBA-BS2.062.D German Release Notice SYSFGM.SBA-BS2.062.E English Release Notice SYSRME.SBA-BS2.062.D German README file SYSRME.SBA-BS2.062.E English README file SYSSDF.SBA-BS2.062 SDF syntax file SYSSII.SBA-BS2.062 Product-specific information for installation via IMON SYSSPR.SBA-BS2.062 Procedures for implementing SDF commands SYSSSC.SBA-BS2.062 Subsystem declaration The following delivery items are only needed on S servers: SYSLNK.SBA-BS2.062 Module library for /390 series

The following delivery items are only needed on SX servers: SPMLNK.SBA-BS2.062 Module library for Sparc Code

The following delivery items are only needed on SQ servers: SKMLNK.SBA-BS2.062 Module library for X86 Code

The SOLIS2 delivery letter lists the valid file and volume attributes.

1.3 Documentation

The following documentation is available for SBA-BS2 V6.2A:

- SNMP Management V6.0 U24387-J-Z135-6-76
 In addition to the extensions of the SBA-BS2 delivery unit, this manual also describe the extensions of the delivery units
 - SNMP standard collection BS2000 (SSC-BS2)
 - SNMP subagent SM2 (SSA-SM2-BS2) and
 - SNMP subagent openUTM (BS2000) (SSA-0UTM-BS2)

You find a complete description in:

- 2. SNMP Management V5.0 U24387-J-Z135-5-76
- 3. A README file, which contains extensions of the manual. When printing these files, the CONTR-CHAR=EBCDIC operand should be specified in the PRINT-FILE command.
- 4. The [present] Release Notice for SBA-BS2 6.2A This Release Notice is also available online under http://manuals.ts.fujitsu.com/mainframes.html.

The documentation is available as online manuals under http://manuals.ts.fujitsu.com

or can be ordered against extra cost under http://manualshop.ts.fujitsu.com

The documentation of the BS2000/OSD standard configuration is also required for operating SBA-BS2.

The BS2000/OSD documentation is also available on CD-ROM in German and English under the title BS2000/OSD SoftBooks.

In addition, for operation of the management station the respective documentation of the manufacturer is also recommended.

2 Software extensions

The following only describes the extensions and/or improvements made in comparison to the prior version SBA-BS2 V6.1A.

SBA-BS2 V6.2A supports the new X86 architecture.

3 Technical information

3.1 Resource requirements

The following memory is required at runtime in the system and user address space:

The master agent uses 5.8 MB main memory. Each subagent uses additionally 2.4 MB.

The product uses approx. 44700 PAM pages of disk space. The disk capacity required in the POSIX files system is negligible.

3.2 Software configuration

```
SBA-BS2 V6.2A requires:
- BS2000/OSD-BC >= V6.0A for /390
- OSD-XC >= V4.0 for SPARC and X86

You must also install:
```

POSIX-BC (contained in BS2000/OSD)
POSIX-Sockets (contained in BS2000/OSD)
IMON (contained in BS2000/OSD)
SDF-P-BASYS (contained in BS2000/OSD)

JV as of V14.0C

3.3 Product installation

The installation of the product with the installation monitor IMON is mandatory. When installing the product, the installation information in the delivery cover letter and the product manual must be noted in addition to that in this Release Notice.

Caution:

The product is automatically installed in the file system of POSIX. Therefore the old version, if available is uninstalled and then the new version is installed.

With the deinstallation of products of version < V6.0A40 the old configuration file /etc/snmp/agt/snmpd.cnf is deleted. Please make a copy of this file if required.

The necessary inputs and the sequence of the installation are described in the IMON documentation.

3.4 Product use

The use of SBA-BS2 V6.2A is described in the User Guide.

The user ID that starts the master agent must also posses the POSIX root authorization in addition to the NET-ADMINISTRATION privilege.

The product is required when other agents are used in BS2000, e.g. agents supplied with openNet Server and openSM2 or the subagents in the delivery units

- SNMP-Standard-Collection BS2000 (SSC-BS2),
- SNMP-Subagent openUTM (BS2000) (SSA-0UTM-BS2) and
- SNMP-Subagent SM2 (SSA-SM2-BS2)

which can be ordered separately.

The use of the product is supported on management side by the free of charge product BS2-SNMP-WIN (Windows), which contains the following packages:

Package	Outline description:
CMBS2	allows the comfortable console operating of all BS2000 systems within a net over graphical user interface.
PMBS2	supports the output of SM2 data supplied by the subagent SSA-SM2-BS2.
CluMon	allows the monitoring of high availability cluster in BS2000/OSD and Reliant Unix.
tclset	Interpreter for the packages mentioned above.

The packages can be found on CD-ROM delivered with SBA-BS2 and can be installed using the conventional installation procedure for packages on Windows.

For extra ordering e.g. correction versions there is the order number U13671-C810.

The packages can also be downloaded from internet: http://ts.fujitsu.com/snmp/snmpmanagement.html

3.5 Obsolete functions

- none -

* 1

- 3.6 Incompatibilities
- none -

3.7 Restrictions

- none -

3.8 Procedure in the event of errors

In the event of errors, the following error documents are required for diagnostic purposes:

- Detailed description of the error event and specifications as to if and how the error can be reproduced;
- Agent log file (SYSTRC.SNMP.<agent>.< date >.< time >) in the user ID under which the agent has been started); if the problem can be reproduced, the agent for creating the log file should be started with
 - /START-SNMP-<agent> ..., TRACE=*APALL
- If the program crashes and a dump is created, this dump is the primary diagnostic document.

4 Hardware support

 $SBA-BS2\ V6.2A$ can be used on all hosts supported by the following $BS2000\ versions:$

```
BS2000/OSD >= V6.0 (/390)
OSD-XC >= V4.0 (SPARC and X86)
```