

Version 5 Release 4

*IBM OMEGAMON for Db2 Performance
Expert on z/OS
Parameter Reference*



2020-09-23 edition

This edition applies to Version 5 Release 4 of IBM® OMEGAMON for DB2® Performance Expert on z/OS (product number 5655-W37) and to all subsequent releases and modifications until otherwise indicated in new editions.

© **Copyright International Business Machines Corporation 2005, 2020.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

© **Rocket Software Inc. 2016, 2020.**

Contents

About this information.....	ix
Chapter 1. OMEGAMON for Db2 Performance Expert overview.....	1
Where to find information.....	1
Service updates and support information.....	2
Accessibility features.....	2
How to send your comments.....	3
Chapter 2. Basic product parameters.....	5
GBL_DB2_KD2_CLASSIC_STC.....	7
GBL_DSN_DB2_DSNEXT.....	8
GBL_DSN_DB2_LOADLIB_V10.....	8
GBL_DSN_DB2_LOADLIB_V11.....	9
GBL_DSN_DB2_LOADLIB_V12.....	10
GBL_DSN_DB2_RUNLIB_V10.....	11
GBL_DSN_DB2_RUNLIB_V11.....	12
GBL_DSN_DB2_RUNLIB_V12.....	12
KD2_CLASSIC_DB2ID_DEFAULT.....	13
KD2_CLASSIC_DB2PM_PLANPKG_OWNER.....	14
KD2_CLASSIC_LROWS.....	16
KD2_CLASSIC_MVS_SYSID.....	17
KD2_CLASSIC_UMAX.....	18
KD2_CLASSIC_USER_PROFILE.....	19
KD2_CLASSIC_VTAM_APPL_LOGON.....	19
KD2_CLASSIC_VTAM_NODE.....	20
KD2_OMPE_AUTH_FAIL.....	21
KD2_OMPE_AUTODETECT.....	21
KD2_OMPE_CCPC_TIMER.....	22
KD2_OMPE_CCPC_TRACE.....	23
KD2_OMPE_CF_REBUILT.....	24
KD2_OMPE_CHECKSYS.....	25
KD2_OMPE_CPU_PARALLEL.....	25
KD2_OMPE_DB2_EVENT.....	26
KD2_OMPE_DB2_EXIT.....	27
KD2_OMPE_DB2_USER.....	28
KD2_OMPE_DEADLOCK.....	28
KD2_OMPE_DSHLQ.....	29
KD2_OMPE_DSN_EXTENT.....	30
KD2_OMPE_DSP_SIZE.....	31
KD2_OMPE_E2E_MON_SPRT.....	32
KD2_OMPE_EDMP_FULL.....	32
KD2_OMPE_EXTENT_THOLD.....	33
KD2_OMPE_GLOBAL_TRACE.....	34
KD2_OMPE_GRANT_AGUSER.....	34
KD2_OMPE_GRANT_EXUSER.....	35
KD2_OMPE_GRANT_PEUSER.....	35
KD2_OMPE_GRANT_PWUSER.....	36
KD2_OMPE_ISPF_LANGUAGE.....	36
KD2_OMPE_LOGSPACE.....	37
KD2_OMPE_MAX_SESSIONS.....	38

KD2_OMPE_MGMTCLAS.....	38
KD2_OMPE_PE_SUPPORT.....	39
KD2_OMPE_RUNALLOC.....	40
KD2_OMPE_SHARED_PROFILE_LIB.....	41
KD2_OMPE_STOCLAS.....	41
KD2_OMPE_SUB_D2PADASP.....	42
KD2_OMPE_SUB_D2PAGRPN.....	43
KD2_OMPE_SUB_D2PARCVT.....	44
KD2_OMPE_SUB_D2PASSIT.....	45
KD2_OMPE_SUB_D2PATSEC.....	45
KD2_OMPE_SUB_D2PAXCFT.....	46
KD2_OMPE_SYSAFF.....	47
KD2_OMPE_TCPIP_ADDRESS.....	48
KD2_OMPE_TCPIP_NAME.....	49
KD2_OMPE_THREAD_COMMIT.....	49
KD2_OMPE_TIMEOUT.....	50
KD2_OMPE_TRACE_LEVEL.....	51
KD2_OMPE_UNIT.....	51
KD2_OMPE_UR.....	52
KD2_OMPE_USE_MODEL.....	53
KD2_OMPE_VOLUME.....	54
KD2_OMPE_VSAM_DSHLQ.....	54
KD2_OMPE_VSAM_MGMTCLAS.....	55
KD2_OMPE_VSAM_STOCLAS.....	56
KD2_OMPE_VSAM_VOLUME.....	56
KD2_PFn_HIS_VSAM_MCLAS1.....	57
KD2_PFn_HIS_VSAM_SCLAS1.....	58
KD2_PFn_HIS_LOG1.....	58
KD2_PFn_HIS_VSAM_VOLUME1.....	59
KD2_PFn_HIS_WHEN_AUTHID.....	60
KD2_PFn_HIS_BUFSIZE.....	61
KD2_PFn_HIS_WHEN_CONNID.....	62
KD2_PFn_HIS_WHEN_CORRID.....	62
KD2_PFn_HIS_COLL_INTV.....	63
KD2_PFn_HIS_SUBINT.....	64
KD2_PFn_HIS_SUBINT_UNIT.....	65
KD2_PFn_HIS_IFIREAD.....	65
KD2_PFn_HIS_WHEN_ORIG.....	66
KD2_PFn_HIS_WHEN_PLAN.....	67
KD2_PFn_HIS_SUSPCOLL.....	67
KD2_PFn_HIS_POSTPCT.....	68
KD2_PFn_HIS_NEQSQL.....	69
KD2_PFn_HIS_DB2_STAT.....	70
KD2_PFn_HIS_START.....	70
KD2_PFn_HIS_SEQ_UNIT1.....	71
KD2_PFn_HIS_DYN_MCLAS.....	72
KD2_PFn_HIS_DYN_SCLAS.....	73
KD2_PFn_HIS_DYN_UNIT.....	73
KD2_PFn_HIS_DYN_VOLUME.....	74
KD2_PFn_HIS_GDG_DSNAME.....	75
KD2_PFn_HIS_GDG_MCLAS.....	75
KD2_PFn_HIS_GDG_SCLAS.....	76
KD2_PFn_HIS_GDG_UNIT.....	77
KD2_PFn_HIS_GDG_VOLUME.....	77
KD2_PFn_HIS_SEQ_ARC_GDGLIM.....	78
KD2_PFn_SQLID.....	79
KD2_PLAN_NAME_OVERRIDE.....	80

Chapter 3. Profile parameters.....	83
How to create DB2 profiles in PARMGEN user profiles.....	83
Object/Volume analysis.....	84
KD2_PFn_OA_ECM.....	84
KD2_PFn_OA_INTV.....	85
KD2_PFn_OA_START.....	86
KD2_PFn_OA_THREAD.....	86
KD2_PFn_OA_WAIT.....	87
Periodic exception processing.....	88
KD2_PFn_AEXCP_D2PYACT.....	88
KD2_PFn_AEXCP_D2TPFDSN.....	89
KD2_PFn_AEXCP_D2TPFDSP.....	89
KD2_PFn_AEXCP_D2TPFLG.....	90
KD2_PFn_AEXCP_D2TPINTV.....	91
KD2_PFn_AEXCP_D2TPLDSN.....	92
KD2_PFn_AEXCP_D2TPLDSP.....	92
KD2_PFn_AEXCP_D2TPLFLG.....	93
KD2_PFn_AEXCP_D2TPTDSN.....	94
KD2_PFn_AEXCP_D2TPTFMC.....	95
KD2_PFn_AEXCP_D2TPTFSC.....	96
KD2_PFn_AEXCP_D2TPUID.....	96
KD2_PFn_AEXCP_D2TPUXIT.....	97
KD2_PFn_AEXCP_D2TPVL.....	98
Parameter Reference - thread history.....	98
KD2_OMPE_VSAM_DSHLQ.....	99
KD2_PFn_HIS_ACCTG_CLAS.....	100
KD2_PFn_HIS_BUFSIZE.....	100
KD2_PFn_HIS_COLL_INTV.....	101
KD2_PFn_HIS_DB2_STAT.....	102
KD2_PFn_HIS_DYN_DSNAME.....	102
KD2_PFn_HIS_DYN_MCLAS.....	103
KD2_PFn_HIS_DYN_PRIMARY.....	104
KD2_PFn_HIS_DYN_SCLAS.....	104
KD2_PFn_HIS_DYN_SECONDARY.....	105
KD2_PFn_HIS_DYN_SQL.....	105
KD2_PFn_HIS_DYN_UNIT.....	106
KD2_PFn_HIS_DYN_VOLUME.....	106
KD2_PFn_HIS_GDG_DSNAME.....	107
KD2_PFn_HIS_GDG_LIM.....	108
KD2_PFn_HIS_GDG_MCLAS.....	108
KD2_PFn_HIS_GDG_PRIMARY.....	109
KD2_PFn_HIS_GDG_SCLAS.....	109
KD2_PFn_HIS_GDG_SECONDARY.....	110
KD2_PFn_HIS_GDG_UNIT.....	110
KD2_PFn_HIS_GDG_VOLUME.....	111
KD2_PFn_HIS_IFIREAD.....	112
KD2_PFn_HIS_LOCK_CNTN.....	113
KD2_PFn_HIS_LOCK_SUSP.....	113
KD2_PFn_HIS_LOG1.....	113
KD2_PFn_HIS_LOG2.....	114
KD2_PFn_HIS_LOG2.....	115
KD2_PFn_HIS_LOG3.....	116
KD2_PFn_HIS_LOG4.....	117
KD2_PFn_HIS_LOG5.....	118
KD2_PFn_HIS_LOG6.....	119
KD2_PFn_HIS_LOG7.....	120

KD2_PFnHIS_NEQSQL.....	121
KD2_PFnHIS_POSTPCT.....	121
KD2_PFnHIS_SCAN_SUMM.....	122
KD2_PFnHIS_SEQLOG1.....	123
KD2_PFnHIS_SEQLOG2.....	123
KD2_PFnHIS_SEQLOG3.....	124
KD2_PFnHIS_SEQLOG4.....	125
KD2_PFnHIS_SEQLOG5.....	125
KD2_PFnHIS_SEQLOG6.....	126
KD2_PFnHIS_SEQLOG7.....	127
KD2_PFnHIS_SEQ_ARC_DS.....	127
KD2_PFnHIS_SEQ_ARC_GDGLIM.....	128
KD2_PFnHIS_SEQ_ARC_MCLAS.....	129
KD2_PFnHIS_SEQ_ARC_SCLAS.....	129
KD2_PFnHIS_SEQ_ARC_TYP.....	130
KD2_PFnHIS_SEQ_ARC_UNIT.....	131
KD2_PFnHIS_SEQ_ARC_VOLUME.....	131
KD2_PFnHIS_SEQ_MCLAS1.....	132
KD2_PFnHIS_SEQ_MCLAS2.....	132
KD2_PFnHIS_SEQ_MCLAS3.....	133
KD2_PFnHIS_SEQ_MCLAS4.....	133
KD2_PFnHIS_SEQ_MCLAS5.....	133
KD2_PFnHIS_SEQ_MCLAS6.....	134
KD2_PFnHIS_SEQ_MCLAS7.....	134
KD2_PFnHIS_SEQ_PRIMARY_CYL.....	135
KD2_PFnHIS_SEQ_SCLAS1.....	135
KD2_PFnHIS_SEQ_SCLAS2.....	136
KD2_PFnHIS_SEQ_SCLAS3.....	136
KD2_PFnHIS_SEQ_SCLAS4.....	137
KD2_PFnHIS_SEQ_SCLAS5.....	137
KD2_PFnHIS_SEQ_SCLAS6.....	138
KD2_PFnHIS_SEQ_SCLAS7.....	138
KD2_PFnHIS_SEQ_SECONDARY_CYL.....	138
KD2_PFnHIS_SEQ_TYP.....	139
KD2_PFnHIS_SEQ_UNIT1.....	140
KD2_PFnHIS_SEQ_UNIT2.....	140
KD2_PFnHIS_SEQ_UNIT3.....	141
KD2_PFnHIS_SEQ_UNIT4.....	142
KD2_PFnHIS_SEQ_UNIT5.....	142
KD2_PFnHIS_SEQ_UNIT6.....	143
KD2_PFnHIS_SEQ_UNIT7.....	143
KD2_PFnHIS_SEQ_VOLUME1.....	144
KD2_PFnHIS_SEQ_VOLUME2.....	144
KD2_PFnHIS_SEQ_VOLUME3.....	145
KD2_PFnHIS_SEQ_VOLUME4.....	146
KD2_PFnHIS_SEQ_VOLUME5.....	146
KD2_PFnHIS_SEQ_VOLUME6.....	147
KD2_PFnHIS_SEQ_VOLUME7.....	148
KD2_PFnHIS_SORT_SUMM.....	148
KD2_PFnHIS_START.....	149
KD2_PFnHIS_STORE.....	149
KD2_PFnHIS_SUBINT.....	150
KD2_PFnHIS_SUBINT_UNIT.....	151
KD2_PFnHIS_SUSPCOLL.....	152
KD2_PFnHIS_VSAM_MB.....	153
KD2_PFnHIS_VSAM_MCLAS1.....	154
KD2_PFnHIS_VSAM_MCLAS2.....	154
KD2_PFnHIS_VSAM_MCLAS3.....	155

KD2_PFn_HIS_VSAM_MCLAS4.....	156
KD2_PFn_HIS_VSAM_MCLAS5.....	157
KD2_PFn_HIS_VSAM_MCLAS6.....	157
KD2_PFn_HIS_VSAM_MCLAS7.....	158
KD2_PFn_HIS_VSAM_SCLAS1.....	159
KD2_PFn_HIS_VSAM_SCLAS2.....	160
KD2_PFn_HIS_VSAM_SCLAS3.....	160
KD2_PFn_HIS_VSAM_SCLAS4.....	161
KD2_PFn_HIS_VSAM_SCLAS5.....	162
KD2_PFn_HIS_VSAM_SCLAS6.....	163
KD2_PFn_HIS_VSAM_SCLAS7.....	163
KD2_PFn_HIS_VSAM_SU.....	164
KD2_PFn_HIS_VSAM_VOLUME1.....	165
KD2_PFn_HIS_VSAM_VOLUME2.....	165
KD2_PFn_HIS_VSAM_VOLUME3.....	166
KD2_PFn_HIS_VSAM_VOLUME4.....	167
KD2_PFn_HIS_VSAM_VOLUME5.....	168
KD2_PFn_HIS_VSAM_VOLUME6.....	168
KD2_PFn_HIS_VSAM_VOLUME7.....	169
KD2_PFn_HIS_WHEN_AUTHID.....	170
KD2_PFn_HIS_WHEN_CONNID.....	171
KD2_PFn_HIS_WHEN_CORRID.....	171
KD2_PFn_HIS_WHEN_ORIG.....	172
KD2_PFn_HIS_WHEN_PLAN.....	173
KD2_PFn_THRDHIS_DYN_SQL.....	173
KD2_PFn_THRDHIS_LOCK_CNTN.....	174
KD2_PFn_THRDHIS_LOCK_SUSP.....	174
KD2_PFn_THRDHIS_LOG_NUM.....	175
KD2_PFn_THRDHIS_SCAN_SUMM.....	175
KD2_PFn_THRDHIS_SORT_SUMM.....	176
Snapshot history (including DB2 Connect Monitoring).....	176
KD2_PFn_DCM_D2SHDCAI.....	176
KD2_PFn_DCM_D2SHDCAP.....	177
KD2_PFn_DCM_D2SHDCSI.....	178
KD2_PFn_DCM_D2SHDCST.....	179
KD2_PFn_SH_D2SHDATA.....	179
KD2_PFn_SH_D2SHDATI.....	180
KD2_PFn_SH_D2SHKHST.....	181
KD2_PFn_SH_D2SHLTHD.....	182
KD2_PFn_SH_D2SHSPAI.....	182
KD2_PFn_SH_D2SHSPAR.....	183
KD2_PFn_SH_D2SHSQLC.....	184
KD2_PFn_SH_D2SHSQLI.....	184
KD2_PFn_SH_D2SHSQLT.....	185
KD2_PFn_SH_D2SHSSZE.....	186
KD2_PFn_SH_D2SHSTAI.....	187
KD2_PFn_SH_D2SHSTAT.....	187
KD2_PFn_SH_D2SHTHDD.....	188
KD2_PFn_SH_D2SHTHDI.....	189
KD2_PFn_SH_D2SQCON1.....	190
KD2_PFn_SH_D2SQCON2.....	190
KD2_PFn_SH_D2SQCON3.....	191
KD2_PFn_SH_D2SQCON4.....	191
KD2_PFn_SH_D2SQCON5.....	192
KD2_PFn_SH_D2SQCON6.....	193
KD2_PFn_SH_D2SQCOR1.....	193
KD2_PFn_SH_D2SQCOR2.....	194
KD2_PFn_SH_D2SQCOR3.....	194

KD2_PFnN_SH_D2SQCOR4.....	195
KD2_PFnN_SH_D2SQCOR5.....	196
KD2_PFnN_SH_D2SQCOR6.....	196
KD2_PFnN_SH_D2SQPLA1.....	197
KD2_PFnN_SH_D2SQPLA2.....	198
KD2_PFnN_SH_D2SQPLA3.....	198
KD2_PFnN_SH_D2SQPLA4.....	199
KD2_PFnN_SH_D2SQPLA5.....	199
KD2_PFnN_SH_D2SQPLA6.....	200
KD2_PFnN_SH_D2SQPRI1.....	201
KD2_PFnN_SH_D2SQPRI2.....	201
KD2_PFnN_SH_D2SQPRI3.....	202
KD2_PFnN_SH_D2SQPRI4.....	202
KD2_PFnN_SH_D2SQPRI5.....	203
KD2_PFnN_SH_D2SQPRI6.....	204
DB2 Explain.....	204
KD2_PFnN_EX_D2EXACT.....	204
KD2_PFnN_EX_D2EXDB.....	205
KD2_PFnN_EX_D2EXOBJ.....	206
KD2_PFnN_EX_D2EXQMF.....	210
KD2_PFnN_EX_D2EXQMFI.....	211
DB2 SQL Performance Analyzer.....	212
KD2_PFnN_SQLPA_CF_ANLC.....	212
KD2_PFnN_SQLPA_CF_ANLP.....	212
KD2_PFnN_SQLPA_CF_ENBL.....	213
KD2_PFnN_SQLPA_ENABLE.....	214
KD2_PFnN_SQLPA_STEPDSN.....	215
KD2_PFnN_SQLPA_VERSION.....	215
Additional DB2 traces.....	216
KD2_PFnN_TRACES_318.....	216
KD2_PFnN_TRACES_400.....	217
KD2_PFnN_TRACES_DB2CMD2.....	218
KD2_PFnN_TRACES_DB2CMD3.....	218
KD2_PFnN_TRACES_DB2CMD4.....	219
Additional monitoring features.....	220
KD2_PFnN_ACS_DB2MSGMON.....	220
KD2_PFnN_READA_OPBUFSIZE.....	220
KD2_PFnN_READA_OPBUFTHR.....	221
KD2_PFnN_READA_SPMON.....	222

Product legal notices..... 225

Index..... 229

About this information

IBM OMEGAMON for Db2 Performance Expert on z/OS (also referred to as OMEGAMON for Db2 Performance Expert) is a performance analysis, monitoring, and tuning tool for Db2 on z/OS® environments.

The document is part of the OMEGAMON for Db2 Performance Expert documentation library which provides instructions for installing, configuring, and using OMEGAMON for Db2 Performance Expert and is designed to help database administrators, system programmers, application programmers, and system operators perform these tasks:

- Plan for the installation of OMEGAMON for Db2 Performance Expert
- Install and operate OMEGAMON for Db2 Performance Expert
- Customize your OMEGAMON for Db2 Performance Expert environment
- Diagnose and recover from OMEGAMON for Db2 Performance Expert problems
- Design and write applications for OMEGAMON for Db2 Performance Expert
- Use OMEGAMON for Db2 Performance Expert with other DB2 products

Tip: To find the most current version of this information, always use [IBM Knowledge Center](#), which is updated more frequently than PDF books.

Chapter 1. OMEGAMON for Db2 Performance Expert overview

OMEGAMON for Db2 Performance Expert is a performance analysis, monitoring, and tuning tool for Db2 on z/OS environments that enables you to perform a variety of tasks such as reporting, trend analysis, and buffer pool analysis.

Where to find information

The OMEGAMON for Db2 Performance Expert documentation set includes the following documents.

Full documentation library (Knowledge Center)

SC27-8803

The OMEGAMON for Db2 Performance Expert Knowledge Center library includes all OMEGAMON for Db2 Performance Expert content.

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/kdp54_welcome.html

Program Directory

GI19-5019

<http://publibfp.dhe.ibm.com/epubs/pdf/i1950190.pdf>

Full documentation library (PDF)

SC27-8803

The IBM OMEGAMON for Db2 Performance Expert User's Guide PDF includes all of the OMEGAMON for Db2 Performance Expert content. It is the PDF version of the Knowledge Center library.

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/kdpuge4.pdf

The OMEGAMON for Db2 Performance Expert documentation is also divided into smaller individual documents for ease-of-use. These documents contain a subset of the topics in the full documentation library.

Planning, Customization, and Migration Guide

GH12-7072

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/ko2cc540.pdf

Buffer Pool Analyzer User's Guide

SH12-7075

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/bpobp540.pdf

Reporting User's Guide

SH12-7071

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/ko2ru540.pdf

Classic Interface User's Guide

SH12-7068

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/ko2ci540.pdf

ISPF Client User's Guide

SH12-7070

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/ko2mi540.pdf

Enhanced 3270 User Interface User's Guide

SH12-7074

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/ko2ui540.pdf

Performance Expert Client User's Guide

SH12-7069

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/ko2mp540.pdf

Report Reference

SH12-7065

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/ko2rr540.pdf

Report Command Reference

SH12-7066

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/ko2rc540.pdf

Parameter Reference

SH12-7073

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/ko2pr540.pdf

Messages and Troubleshooting Guide

GH12-7067

https://www.ibm.com/support/knowledgecenter/SSUSPS_5.4.0/kdp54/ko2me540.pdf

Other documents

These OMEGAMON for Db2 Performance Expert documents are available for users who need information about special topics.

Quick Start Guide - GI19-5019

Quick start information for the SQL Dashboard and the end-to-end SQL monitoring functions.

<http://publibfp.dhe.ibm.com/epubs/pdf/h1270640.pdf>

DB2 Performance Expert for Multiplatforms

SG24-6867

A guide to installing, configuring, and using OMEGAMON for Db2 Performance Expert.

<http://www.redbooks.ibm.com/redbooks/pdfs/sg246470.pdf>

Service updates and support information

You can access support information for IBM Tivoli® OMEGAMON® for Db2 Performance Expert on z/OS and IBM OMEGAMON for Db2 Performance Monitor on z/OS on the Support home website, or you can use the IBM Support Assistant.

Support home

On the [Support home](#) website, you can find service updates and support information including software fix packs, PTFs, Frequently Asked Questions (FAQs), technical notes, troubleshooting information, and downloads.

Accessibility features

Accessibility features help people with a physical disability, such as restricted mobility or limited vision, or with other special needs, to use software products successfully. This Knowledge Center is developed to comply with the accessibility requirements of software products according to Section 508 of the Rehabilitation Act of the United States.

The accessibility features in this Knowledge Center enable users to do the following tasks:

- Use assistive technologies, such as screen-reader software and digital speech synthesizer, to hear what is displayed on the screen. In this Knowledge Center, all information is provided in HTML format. Consult the product documentation of the assistive technology for details on using assistive technologies with HTML-based information.
- Operate specific or equivalent features using only the keyboard.
- Magnify what is displayed on the screen.

In addition, all images are provided with alternative text so that users with vision impairments can understand the contents of the images.

Navigating the interface by using the keyboard

Standard shortcut and accelerator keys are used by the product and are documented by the operating system. Refer to the documentation provided by your operating system for more information.

Magnifying what is displayed on the screen

You can enlarge information in the product windows using facilities provided by the operating systems on which the product is run. For example, in a Microsoft Windows environment, you can lower the resolution of the screen to enlarge the font sizes of the text on the screen. Refer to the documentation provided by your operating system for more information.

How to send your comments

Your feedback is important in helping to provide the most accurate and high-quality information.

If you have any comments about this information or any other documentation, you can complete and submit the [*Reader Comment Form*](#).

Chapter 2. Basic product parameters

This section lists the basic parameters of OMEGAMON for Db2 PE.

The basic setup of OMEGAMON for Db2 PE covers the configuration of the OMEGAMON Collector, the configuration of the user interfaces, and the configuration of the monitoring functions that are enabled globally for all DB2 subsystems.

This section contains a number of parameters to configure the server and the user interfaces. The following table distinguishes between the server-related parameters and the user interface parameters. This information will help you to know which parameters need to be configured in order to use a specific user interface.

Table 1. Overview: Components and corresponding parameter names

Component	Parameter
Global control and OMEGAMON Collector information parameters	“GBL_DB2_KD2_CLASSIC_STC” on page 7
	“GBL_DSN_DB2_DSNEXIT” on page 8
	“GBL_DSN_DB2_LOADLIB_V10” on page 8
	“GBL_DSN_DB2_LOADLIB_V11” on page 9
	“GBL_DSN_DB2_LOADLIB_V12” on page 10
	“GBL_DSN_DB2_RUNLIB_V10” on page 11
	“GBL_DSN_DB2_RUNLIB_V11” on page 12
	“GBL_DSN_DB2_RUNLIB_V12” on page 12
	“KD2_CLASSIC_DB2PM_PLANPKG_OWNER” on page 14
	“KD2_CLASSIC_MVS_SYSID” on page 17
	“KD2_OMPE_CCPC_TIMER” on page 22
	“KD2_OMPE_CCPC_TRACE” on page 23
	“KD2_OMPE_CHECKSYS” on page 25
	“KD2_OMPE_DB2_EXIT” on page 27
	“KD2_OMPE_DB2_USER” on page 28
	“KD2_OMPE_DSHLQ” on page 29
	“KD2_OMPE_MGMTCLAS” on page 38
	“KD2_OMPE_RUNALLOC” on page 40
	“KD2_OMPE_SHARED_PROFILE_LIB” on page 41
	“KD2_OMPE_STOCLAS” on page 41
	“KD2_OMPE_SUB_D2PADASP” on page 42
	“KD2_OMPE_SUB_D2PAGRPN” on page 43
	“KD2_OMPE_SUB_D2PARCVT” on page 44
	“KD2_OMPE_SUB_D2PASSIT” on page 45
	“KD2_OMPE_SUB_D2PATSEC” on page 45
	“KD2_OMPE_SUB_D2PAXCFT” on page 46
“KD2_OMPE_SYSAFF” on page 47	
“KD2_OMPE_TRACE_LEVEL” on page 51	
“KD2_OMPE_UNIT” on page 51	
“KD2_OMPE_USE_MODEL” on page 53	
“KD2_OMPE_VOLUME” on page 54	
“KD2_OMPE_VSAM_DSHLQ” on page 54	
“KD2_OMPE_VSAM_MGMTCLAS” on page 55	
“KD2_OMPE_VSAM_STOCLAS” on page 56	
“KD2_OMPE_VSAM_VOLUME” on page 56	

Table 1. Overview: Components and corresponding parameter names (continued)

Component	Parameter
Event exception processing	“KD2_OMPE_AUTH_FAIL” on page 21
	“KD2_OMPE_CF_REBUILT” on page 24
	“KD2_OMPE_DB2_EVENT” on page 26
	“KD2_OMPE_DEADLOCK” on page 28
	“KD2_OMPE_DSN_EXTENT” on page 30
	“KD2_OMPE_EDMP_FULL” on page 32
	“KD2_OMPE_EXTENT_THOLD” on page 33
	“KD2_OMPE_GLOBAL_TRACE” on page 34
	“KD2_OMPE_LOGSPACE” on page 37
	“KD2_OMPE_THREAD_COMMIT” on page 49
	“KD2_OMPE_TIMEOUT” on page 50
“KD2_OMPE_UR” on page 52	
CPU parallelism	“KD2_OMPE_CPU_PARALLEL” on page 25
	“KD2_OMPE_DSP_SIZE” on page 31
Classic interface	“KD2_CLASSIC_DB2ID_DEFAULT” on page 13
	“KD2_CLASSIC_LROWS” on page 16
	“KD2_CLASSIC_UMAX” on page 18
	“KD2_CLASSIC_USER_PROFILE” on page 19
	“KD2_CLASSIC_VTAM_APPL_LOGON” on page 19
	“KD2_CLASSIC_VTAM_NODE” on page 20
ISPF monitoring dialogs	“KD2_OMPE_ISPF_LANGUAGE” on page 36
Performance Expert Client and end-to-end SQL monitoring	“KD2_OMPE_E2E_MON_SPRT” on page 32
	“KD2_OMPE_MAX_SESSIONS” on page 38
	“KD2_OMPE_PE_SUPPORT” on page 39
	“KD2_OMPE_TCPIP_ADDRESS” on page 48
	“KD2_OMPE_TCPIP_NAME” on page 49

GBL_DB2_KD2_CLASSIC_STC

OMEGAMON Collector started task

Description

The name of the OMEGAMON Collector started task. This name should conform to any security facility in place in your installation.

Required or optional

Required

Default value

%RTE_STC_PREFIX%D2

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)

Panel name

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

Started task

Default value

&RTESTCP.O2

Batch parameter name

KD2_CLA_STC

PARMGEN name

GBL_DB2_KD2_CLASSIC_STC

PARMGEN classification

CLA

GBL_DSN_DB2_DSNEXIT

DB2 exit library

Description

The name of the dataset in which the DB2 exit load modules reside that should be used by the OMEGAMON Collector.

Required or optional

Optional

Default value

DSN.V9R1M0.DSNEXIT

Location where the parameter value is stored

In the &O2CINAME member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

```
// DD DISP=SHR,DSN=<value>
```

In the Configuration Tool (ICAT)**Panel name**

DB2 Libraries

Panel ID

KD261P0

Panel field

Specify a DB2 exit library

Default value

None

Batch parameter name

KD2_OMPE_DB2EXIT

PARMGEN name

GBL_DSN_DB2_DSNEXIT

PARMGEN classification

DB2

GBL_DSN_DB2_LOADLIB_V10

Load library for DB2 Version 10

Description

The name of the dataset in which the DB2 load modules reside. Specify one DB2 load library for each DB2 subsystem version that you want to monitor.

Required or optional

Optional

Default value

DSN.VAR1M0.SDSNLOAD

Locations where the parameter value is stored**Location 1**In the &O2CINAME member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

// DD DISP=SHR,DSN=<value>

Location 2In the &O2CINAME member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

<value> +

Location 3In the CRTDB2M member of the *rhilev.midlev.rtename.RKD2PRF* library**Output line**

<value> +

In the Configuration Tool (ICAT)**Panel name**

DB2 Libraries

Panel ID

KD261P0

Panel field

DB2 Version 10

Default value

None

Batch parameter name

KD2_OMPE_DB2LOADLIB_V10

PARMGEN name

GBL_DSN_DB2_LOADLIB_V10

PARMGEN classification

DB2

GBL_DSN_DB2_LOADLIB_V11

Load library for DB2 Version 11

Description

The name of the dataset in which the DB2 load modules reside. Specify one DB2 load library for each DB2 subsystem version that you want to monitor.

Required or optional

Optional

Default value

None

Locations where the parameter value is stored**Location 1**In the &O2CINAME member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

// DD DISP=SHR,DSN=<value>

Location 2

In the &O2CINAME member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

<value> +

Location 3

In the CRTDB2M member of the *rhilev.midlev.rtename.RKD2PRF* library

Output line

<value> +

In the Configuration Tool (ICAT)**Panel name**

DB2 Libraries

Panel ID

KD261P0

Panel field

DB2 Version 11

Default value

None

Batch parameter name

KD2_OMPE_DB2LOADLIB_V11

PARMGEN name

GBL_DSN_DB2_LOADLIB_V11

PARMGEN classification

DB2

GBL_DSN_DB2_LOADLIB_V12

Load library for DB2 Version 12

Description

The name of the dataset in which the DB2 load modules reside. Specify one DB2 load library for each DB2 subsystem version that you want to monitor.

Required or optional

Optional

Default value

None

Locations where the parameter value is stored**Location 1**

In the &O2CINAME member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

// DD DISP=SHR,DSN=<value>

Location 2

In the &O2CINAME member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

<value> +

Location 3

In the CRTDB2M member of the *rhilev.midlev.rtename.RKD2PRF* library

Output line

<value> +

In the Configuration Tool (ICAT)

Panel name

DB2 Libraries

Panel ID

KD261P0

Panel field

DB2 Version 12

Default value

None

Batch parameter name

KD2_OMPE_DB2LOADLIB_V12

PARMGEN name

GBL_DSN_DB2_LOADLIB_V12

PARMGEN classification

DB2

GBL_DSN_DB2_RUNLIB_V10

Run library for DB2 Version 10

Description

The name of the dataset in which the DB2 RUNLIB load modules reside. Specify one DB2 run library for each DB2 subsystem version that you want to monitor.

This library should contain the modules DSNTIAD and DSNTIAUL to be used to run in batch. The run library is used to generate GRANT and BIND jobs that prepare the DB2 subsystems for monitoring. See Complete the configuration for details.

Required or optional

Optional

Default value

DSN.VAR1M0.RUNLIB

Locations where the parameter value is stored

Location 1

In the &O2CINAME member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

<value> +

Location 2

In the CRTDB2M member of the *rhilev.midlev.rtename.RKD2PRF* library

Output line

<value> +

In the Configuration Tool (ICAT)

Panel name

DB2 Libraries

Panel ID

KD261P0

Panel field

DB2 Version 10

Default value

None

Batch parameter name

KD2_OMPE_DB2RUNLIB_V10

PARMGEN name

GBL_DSN_DB2_RUNLIB_V10

PARMGEN classification

DB2

GBL_DSN_DB2_RUNLIB_V11

Run library for DB2 Version 11

Description

The name of the dataset in which the DB2 RUNLIB load modules reside. Specify one DB2 run library for each DB2 subsystem version that you want to monitor.

This library should contain the modules DSNTIAD and DSNTIAUL to be used to run in batch. The run library is used to generate GRANT and BIND jobs that prepare the DB2 subsystems for monitoring. See Complete the configuration for details.

Required or optional

Optional

Default value

None

Locations where the parameter value is stored**Location 1**In the &O2CINAME member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

<value> +

Location 2In the CRTDB2M member of the *rhilev.midlev.rtename.RKD2PRF* library**Output line**

<value> +

In the Configuration Tool (ICAT)**Panel name**

DB2 Libraries

Panel ID

KD261P0

Panel field

DB2 Version 11

Default value

None

Batch parameter name

KD2_OMPE_DB2RUNLIB_V11

PARMGEN name

GBL_DSN_DB2_RUNLIB_V11

PARMGEN classification

DB2

GBL_DSN_DB2_RUNLIB_V12

Run library for DB2 Version 12

Description

The name of the dataset in which the DB2 RUNLIB load modules reside. Specify one DB2 run library for each DB2 subsystem version that you want to monitor.

This library should contain the modules DSNTIAD and DSNTIAUL to be used to run in batch. The run library is used to generate GRANT and BIND jobs that prepare the DB2 subsystems for monitoring. See Complete the configuration for details.

Required or optional

Optional

Default value

None

Locations where the parameter value is stored

Location 1

In the &O2CINAME member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

<value> +

Location 2

In the CRTDB2M member of the *rhilev.midlev.rtename.RKD2PRF* library

Output line

<value> +

In the Configuration Tool (ICAT)

Panel name

DB2 Libraries

Panel ID

KD261P0

Panel field

DB2 Version 12

Default value

None

Batch parameter name

KD2_OMPE_DB2RUNLIB_V12

PARMGEN name

GBL_DSN_DB2_RUNLIB_V12

PARMGEN classification

DB2

KD2_CLASSIC_DB2ID_DEFAULT

Default DB2 ID

Description

Specify the default DB2 subsystem ID for real-time VTAM mode connection. When you log on to Classic Interface, this is the default DB2 subsystem to be monitored.

With datasharing group support, a new value for the default DB2 ID was introduced NONE. If you specify NONE and log on to Classic Interface, you are routed to the ZRLOG panel that lists all DB2 subsystems with status information and allows you to select the DB2 subsystems that you want to monitor. NONE is used as the default value.

Required or optional

Required

Default value

NONE

Locations where the parameter value is stored

Location 1

In the KD2COLLP member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

DEFAULT_DB2_SUBSYSTEM(<value>)

Location 2

In the RVTMssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

DB2=<value>, !X

Location 3

In the &O2CINAME member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

EXEC RVTM<value>

In the Configuration Tool (ICAT)**Panel name**

Classic Interface Information

Panel ID

KD261PO

Panel field

Default DB2 ID for real-time VTAM mode

Default value

NONE

Batch parameter name

KD2_CLA_DB2ID_DFLT

PARMGEN name

KD2_CLASSIC_DB2ID_DEFAULT

PARMGEN classification

CLA

KD2_CLASSIC_DB2PM_PLANPKG_OWNER

OMEGAMON Collector plan/package owner

Description

The OMEGAMON Collector plan/package owner is the USERID/GROUPID that will be granted the authority to administrate the OMEGAMON Collector, for example to rebind the DB2 packages. This USERID/GROUPID is specified as the OWNER of the OMEGAMON Collector's plan and packages when the plan and the packages are bound.

Required or optional

Required

Default value

DB2PM

Locations where the parameter value is stored**Location 1**

In the CRTDB2 member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

<value> +

Location 2

In the CRTDB2M member of the *rhilev.midlev.rtename*.RKD2PRF library

Output line

<value> +

Location 3

In the CRTDB2M member of the *rhilev.midlev.rtename*.RKD2PRF library

Output line

<value> +

Location 4

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

GRANT SELECT ON SYSIBM.SYSINDEXES TO <value>;

Location 5

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

GRANT SELECT ON SYSIBM.SYSPACKSTMT TO <value>;

Location 6

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

GRANT SELECT ON SYSIBM.SYSTABLES TO <value>;

Location 7

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

GRANT SELECT ON SYSIBM.SYSSTMT TO <value>;

Location 8

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

GRANT SELECT ON SYSIBM.SYSPLAN TO <value>;

Location 9

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

GRANT SELECT ON SYSIBM.SYSUSERAUTH TO <value>;

Location 10

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

GRANT PACKADM ON COLLECTION K020M510 TO <value>;

Location 11

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

GRANT SELECT ON SYSIBM.SYSTABLE0SPACE TO <value>;

Location 12

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

GRANT SELECT ON SYSIBM.SYSSYNONYMS TO <value>;

Location 13

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

GRANT BINDADD TO <value>;

Location 14

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

GRANT SELECT ON SYSIBM.SYSDBRM TO <value>;

Location 15

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSPACKAGE TO <value>;
```

Location 16

In the OMGRssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
GRANT SELECT ON SYSIBM.SYSDATABASE TO <value>;
```

Location 17

In the OMGRssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
GRANT SELECT ON SYSIBM.SYSSTRINGS TO <value>;
```

In the Configuration Tool (ICAT)**Panel name**

Global Control Parameters

Panel ID

KD261PI

Panel field

OMEGAMON Collector plan/package owner

Default value

DB2PM

Batch parameter name

KD2_CLA_SEC_AUTH_CLAS

PARMGEN name

KD2_CLASSIC_DB2PM_PLANPKG_OWNER

PARMGEN classification

CLA

KD2_CLASSIC_LROWS

Number of logical rows

Description

LROWS specifies the number of logical rows that are available for the output area on the Classic Interface. The number of logical rows should always be set to a number greater than the number of rows to be displayed on the terminal. The default for LROWS is 255.

Increasing the number of logical rows results in higher storageconsumption.

Required or optional

Required

Default value

255

Minimum

99

Maximum

9999

Location where the parameter value is stored

In the RVTMssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

```
LROWS=<value>, !X
```

In the Configuration Tool (ICAT)

Panel name

Classic Interface Information

Panel ID

KD261PO

Panel field

Number of logical rows (LROWS)

Default value

255

Minimum

99

Maximum

9999

Batch parameter name

KD2_CLA_LROWS

PARMGEN name

KD2_CLASSIC_LROWS

PARMGEN classification

CLA

KD2_CLASSIC_MVS_SYSID

z/OS system ID

Description

The name of the z/OS system that the DB2 subsystem runs on. The z/OS system name that you specify here is used to replace the %SY% variable in data set names. If you specify a data set name for a monitoring profile, for example the name of a Near-Term History VSAM log data set, you can use %SY% as a variable for the z/OS system name. If you enable 'Add JES2 JOBPARM SYSAFF to jobs' (KD2_OMPE_SYSAFF), the z/OS system name is used to generate the SYSAFF parameter in the jobcards of the BIND and GRANT jobs generated for the different DB2 subsystems.

Required or optional

Required

Default value

PARMGEN provided SMFID symbol

Locations where the parameter value is stored**Location 1**

In the CRTDB2 member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
/*JOBPARM SYSAFF=<value>
```

Location 2

In the CRTDB2M member of the *rhilev.midlev.rtename.RKD2PRF* library

Output line

```
/*JOBPARM SYSAFF=<value>
```

Location 3

In the DB2PROF member of the *rhilev.midlev.rtename.RKD2PRF* library

Output line

```
DB2_SYSID=<value>
```

In the Configuration Tool (ICAT)

Panel name

Global Control Parameters

Panel ID

KD261PI

Panel field

z/OS system ID (SMFID)

Default value

SYSA

Batch parameter name

KD2_CLA_MVS_SYSID

PARMGEN name

KD2_CLASSIC_MVS_SYSID

PARMGEN classification

CLA

KD2_CLASSIC_UMAX

Maximum number of users

Description

UMAX specifies the maximum number of concurrent sessions the collector can support. The default is 99.

Make sure that you specify enough sessions to support all menusystem and OMEGAVIEW sessions for multiple DB2 subsystems.

Required or optional

Required

Default value

99

Minimum

1

Maximum

99

Location where the parameter value is stored

In the RVTMssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

UMAX=<value>, !X

In the Configuration Tool (ICAT)

Panel name

Classic Interface Information

Panel ID

KD261PO

Panel field

Maximum number of users (UMAX)

Default value

99

Minimum

1

Maximum

99

Batch parameter name

KD2_CLA_UMAX

PARMGEN name

KD2_CLASSIC_UMAX

PARMGEN classification

CLA

KD2_CLASSIC_USER_PROFILE

Profile ID

Description

USER specifies the 2-character profile ID that is to be used for the Classic Interface session. A default profile with the profile ID #P is provided by IBM.

In the profile the configuration options for the ClassicInterface session are specified. You can create a customized profile. To create a new profile, log on to the Classic Interface, modify the selected profile options and save the adjusted profile specifying a 2-character profile ID. If the profile you specified for USER does not exist, the Classic Interface uses the default profile /C for the logon. So you can specify a profile ID for USER now and create the new profile at the first logon to Classic Interface.

Required or optional

Required

Default value

#P

Location where the parameter value is storedIn the RVTMssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

USER=<value>, !X

In the Configuration Tool (ICAT)**Panel name**

Classic Interface Information

Panel ID

KD261PO

Panel field

Profile ID (USER)

Default value

#P

Batch parameter name

KD2_CLA_USER

PARMGEN name

KD2_CLASSIC_USER_PROFILE

PARMGEN classification

CLA

KD2_CLASSIC_VTAM_APPL_LOGON

Classic VTAM logon applid

Description

This specifies a 1-to-8 character name, that will define OBVTAM as an application to VTAM.

Required or optional

Required

Default value

%RTE_VTAM_APPLID_PREFIX%D2C

Location where the parameter value is stored

In the &RTENAME member of the *rhilev.midlev.rtename*.RKANPARU library

Output line

KD2_CLA_VTM_APPL_LOGON!<value>

In the Configuration Tool (ICAT)**Panel name**

Classic Interface Information

Panel ID

KD261PO

Panel field

Classic logon

Default value

None

Batch parameter name

KD2_CLA_VTM_APPL_LOGON

PARMGEN name

KD2_CLASSIC_VTAM_APPL_LOGON

PARMGEN classification

CLA

KD2_CLASSIC_VTAM_NODE

Classic VTAM major node

Description

This specifies the OBVTAM application major node name.

This name is used as the member name to create the OBVTAM VTAM definition in the RKD2SAM library. This member must be moved to SYS1.VTAMLST.

Required or optional

Required

Default value

%RTE_VTAM_APPLID_PREFIX%D2N2

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)**Panel name**

Classic Interface Information

Panel ID

KD261PO

Panel field

Major node

Default value

None

Batch parameter name

KD2_CLA_VTM_NODE

PARMGEN name

KD2_CLASSIC_VTAM_NODE

PARMGEN classification

CLA

KD2_OMPE_AUTH_FAIL

Authorization failure

Description

Used to specify whether authorization fail events data collection is started.

Required or optional

Optional (Required in case KD2_OMPE_DB2_EVENT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

EVENTAUTHFAIL=<value>

In the Configuration Tool (ICAT)**Panel name**

DB2 Event Exception Processing

Panel ID

KD261PG

Panel field

Authorization failure

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_OMPE_AUTH_FAIL

PARMGEN name

KD2_OMPE_AUTH_FAIL

PARMGEN classification

OMPE

KD2_OMPE_AUTODETECT

Enable autom. DB2 subsystem detection

Description

This feature is part of the OMEGAMON Collector PESERVER subtask. If activated, all active DB2 subsystems in the LPAR are detected automatically, regardless of whether the DB2 subsystem has been explicitly configured during the configuration process or not. You can activate or deactivate this feature:

Y

Automatic detection is activated. Detection of all active DB2 subsystems starts automatically.

N

Automatic detection is deactivated. Only the DB2 subsystems that are explicitly configured are monitored.

If a DB2 subsystem has been detected automatically but has not been configured so far, monitoring is not possible because required bind and grant jobs have not been submitted. Error messages are written to the job log. To enable monitoring the subsystem must be configured as usually with PARMGEN to create the required jobs. The configuration steps of Complete the Configuration must be executed.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

AUTODETECT=<value>

In the Configuration Tool (ICAT)

Panel name

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

Automatic DB2 subsystem monitoring

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_OMPE_AUTODETECT

PARMGEN name

KD2_OMPE_AUTODETECT

PARMGEN classification

OMPE

KD2_OMPE_CCPC_TIMER

TEMA connection timeout interval

Description

This timeout interval is used to control the amount of time that a TEMA connect or TEMA collect call remains pending while collecting the data from a target DB2 subsystem is not completed. The TEMA is notified when the call exceeds the specified timeout interval. Specify a value in the range of 0010-0300. 0010 represents ten seconds and 0300 represents three minutes.

Required or optional

Required

Default value

0030

Minimum

0010

Maximum

0300

Locations where the parameter value is stored

Location 1

In the OMPECCPC member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

```
START COMMCOLL, PARM=(TRACE=YES, STIMER=00<value>.00, SLX=REUSE)
```

Location 2

In the OMPECCPC member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

```
START COMMCOLL, PARM=(TRACE=NO, STIMER=00<value>.00, SLX=REUSE)
```

In the Configuration Tool (ICAT)

Panel name

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

TEMA connection timeout interval

Default value

0030

Minimum

0010

Maximum

0300

Batch parameter name

KD2_OMPE_CCPC_TIMER

PARMGEN name

KD2_OMPE_CCPC_TIMER

PARMGEN classification

OMPE

KD2_OMPE_CCPC_TRACE

TEMA connection trace

Description

Enables tracing of the status of OMEGAMON XE for DB2 Agent (TEMA) connect, collect, and disconnect calls. Specify one of the following values:

Y

Trace messages are written to the joblog of the OMEAGMON Collector.

N

No trace messages on the TEMA connection status are written to the OMEGAMON Collector joblog.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)

Panel name

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

TEMA connection trace

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_OMPE_CCPC_TRACE

PARMGEN name

KD2_OMPE_CCPC_TRACE

PARMGEN classification

OMPE

KD2_OMPE_CF_REBUILT

CF rebuilt

Description

Used to specify whether coupling facility rebuild data collection is started.

Required or optional

Optional (Required in case KD2_OMPE_DB2_EVENT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

EVENTCFREBUILD=<value>

In the Configuration Tool (ICAT)

Panel name

DB2 Event Exception Processing

Panel ID

KD261PG

Panel field

CF rebuilt

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_OMPE_CF_REBUILT

PARMGEN name

KD2_OMPE_CF_REBUILT

PARMGEN classification

OMPE

KD2_OMPE_CHECKSYS

Use this RTE as a model

Description

Specify whether you want to use this RTE as a model for several LPARs:

Y

You can specify DB2 subsystems in this RTE that run on different LPARs. Specify the respective z/OS system ID (SMFID) for each DB2 subsystem. When you later submit the 'Create DB2 runtime members' job, this configuration job checks on which LPAR it is executed and only generates the runtime members for the configured DB2 subsystems that run on this LPAR.

N

You configure only DB2 subsystems in this RTE that run on one LPAR. You don't have to specify a z/OS system ID (SMFID) for each DB2 subsystem.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the CRTDB2M member of the *rhilev.midlev.rtename.RKD2PRF* library

Output line

<value> +

In the Configuration Tool (ICAT)

Panel name

Global Control Parameters

Panel ID

KD261PI

Panel field

Use this RTE as a model

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_OMPE_CHECKSYS

PARMGEN name

KD2_OMPE_CHECKSYS

PARMGEN classification

OMPE

KD2_OMPE_CPU_PARALLEL

Enable CPU Parallelism

Description

Used to enable or disable the collection of query CPU parallelism data. Specify one of the following values:

Y

Query CP parallelism data is to be collected.

N

Query CP parallelism data is not to be collected.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

COLLECTCPUPARALLEL=<value>

In the Configuration Tool (ICAT)

Panel name

CPU Parallelism

Panel ID

KD261PF

Panel field

Enable CPU Parallelism data collection

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_OMPE_CPU_PARALLEL

PARMGEN name

KD2_OMPE_CPU_PARALLEL

PARMGEN classification

OMPE

KD2_OMPE_DB2_EVENT

Enable Event Exception Processing

Description

Used to specify whether DB2 event data is to be collected. Specify one of the following values:

Y

DB2 event data is collected.

N

DB2 event data is not collected.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

EVENTOBSERVATION=<value>

In the Configuration Tool (ICAT)**Panel name**

DB2 Event Exception Processing

Panel ID

KD261PG

Panel field

Enable DB2 event exception processing

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_OMPE_DB2_EVENT

PARMGEN name

KD2_OMPE_DB2_EVENT

PARMGEN classification

DB2

KD2_OMPE_DB2_EXIT

Use DB2 authorization exit

Description

This specifies whether the DB2 authorization exit is called.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

USEDDB2AUTHEXIT=<value>

In the Configuration Tool (ICAT)**Panel name**

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

Use DB2 authorization exit

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_OMPE_DB2_EXIT

PARMGEN name

KD2_OMPE_DB2_EXIT

PARMGEN classification

DB2

KD2_OMPE_DB2_USER

Enable OMEGAMON Collector user exit

Description

Used to specify whether the user exit routine DGOVUUAE provided by OMEGAMON XE for DB2 PE shall be used. Specify one of the following values:

Y

The user-modifiable exit routine DGOVUUAE is called.

N

The user-modifiable exit is not called.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OPPEMSTR member of the *rhilev.middlev.rtename*.RKD2PAR library

Output line

USEUSERAUTHEXIT=<value>

In the Configuration Tool (ICAT)**Panel name**

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

Enable OMEGAMON Collector user exit

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_OMPE_DB2_USER

PARMGEN name

KD2_OMPE_DB2_USER

PARMGEN classification

DB2

KD2_OMPE_DEADLOCK

Deadlock

Description

Used to specify whether deadlock events data collection is started.

Required or optional

Optional (Required in case KD2_OMPE_DB2_EVENT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

EVENTDEADLOCK=<value>

In the Configuration Tool (ICAT)**Panel name**

DB2 Event Exception Processing

Panel ID

KD261PG

Panel field

Deadlock

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_OMPE_DEADLOCK

PARMGEN name

KD2_OMPE_DEADLOCK

PARMGEN classification

OMPE

KD2_OMPE_DSHLQ

HLQ for OM Collector datasets

Description

This parameter specifies the high-level qualifier for the data sets that are allocated by the OMEGAMON Collector.

The default value is generated from the high-level qualifier and the mid-level qualifier that you specified for your RTE.

Required or optional

Required

Default value

%RTE_HILEV%.%RTE_NAME%

Locations where the parameter value is stored**Location 1**

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

VDATASERVERHLQ=<value>V

Location 2

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

DATASERVERHLQ=<value>

Location 3

In the OMDDssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
DEFINE CLUSTER(NAME(<value>V..%DB%.HISTORY) -
```

Location 4

In the OMDDssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
DELETE (<value>V..%DB%.HISTORY) CLUSTER
```

In the Configuration Tool (ICAT)**Panel name**

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

High-level Qualifier

Default value

None

Batch parameter name

KD2_OMPE_DSHLQ

PARMGEN name

KD2_OMPE_DSHLQ

PARMGEN classification

OMPE

KD2_OMPE_DSN_EXTENT

Data set extent

Description

Used to specify whether data set extension events data collection is started.

Required or optional

Optional (Required in case KD2_OMPE_DB2_EVENT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

```
EVENTDSEXTENT=<value>
```

In the Configuration Tool (ICAT)**Panel name**

DB2 Event Exception Processing

Panel ID

KD261PG

Panel field

Data set extent

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_OMPE_DSN_EXTENT

PARMGEN name

KD2_OMPE_DSN_EXTENT

PARMGEN classification

OMPE

KD2_OMPE_DSP_SIZE

Data Space size

Description

Used to specify the size of the CCP data space. The value is the data space size in megabytes. This data space is needed when query CP parallelism is active. The default is 20.

Required or optional

Optional (Required in case KD2_OMPE_CPU_PARALLEL is set to Y)

Default value

20

Minimum

5

Maximum

50

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

CCPDATASPACE SIZE=<value>

In the Configuration Tool (ICAT)**Panel name**

CPU Parallelism

Panel ID

KD261PF

Panel field

Data space size

Default value

20

Minimum

5

Maximum

50

Batch parameter name

KD2_OMPE_DSP_SIZE

PARMGEN name

KD2_OMPE_DSP_SIZE

PARMGEN classification

OMPE

KD2_OMPE_E2E_MON_SPRT

Enable end-to-end SQL monitoring support

Description

Used to specify whether the end-to-end SQL monitoring support is to be configured. Specify one of the following values:

Y

The end-to-end SQL monitoring support is enabled

N

The end-to-end SQL monitoring support is disabled

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

TCPIP=<value>

In the Configuration Tool (ICAT)

Panel name

Workstation Interface Support

Panel ID

KD261PC

Panel field

Enable end-to-end SQL monitoring support

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_OMPE_E2E_MON_SPRT

PARMGEN name

KD2_OMPE_E2E_MON_SPRT

PARMGEN classification

OMPE

KD2_OMPE_EDMP_FULL

EDM pool full

Description

Used to specify whether EDM events data collection is started.

Required or optional

Optional (Required in case KD2_OMPE_DB2_EVENT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

EVENTEDMPOOL=<value>

In the Configuration Tool (ICAT)**Panel name**

DB2 Event Exception Processing

Panel ID

KD261PG

Panel field

EDM pool full

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_OMPE_EDMP_FULL

PARMGEN name

KD2_OMPE_EDMP_FULL

PARMGEN classification

OMPE

KD2_OMPE_EXTENT_THOLD

Data set extent threshold

Description

Used to specify the number of extensions that must be exceeded before an extent threshold exception is reported.

Required or optional

Optional (Required in case KD2_OMPE_DB2_EVENT is set to Y)

Default value

200

Minimum

1

Maximum

200

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

EVENTDSEXTENTQUAL=<value>

In the Configuration Tool (ICAT)**Panel name**

DB2 Event Exception Processing

Panel ID

KD261PG

Panel field

Data set extent threshold

Default value

200

Minimum

1

Maximum

200

Batch parameter name

KD2_OMPE_EXTENT_THOLD

PARMGEN name

KD2_OMPE_EXTENT_THOLD

PARMGEN classification

OMPE

KD2_OMPE_GLOBAL_TRACE

Global trace started

Description

Used to specify whether all entered DB2 commands collection is started.

Required or optional

Optional (Required in case KD2_OMPE_DB2_EVENT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is storedIn the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

EVENTGLBLTRACE=<value>

In the Configuration Tool (ICAT)**Panel name**

DB2 Event Exception Processing

Panel ID

KD261PG

Panel field

Global trace started

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_OMPE_GLOBAL_TRACE

PARMGEN name

KD2_OMPE_GLOBAL_TRACE

PARMGEN classification

OMPE

KD2_OMPE_GRANT_AGUSER

User ID/group ID for PWGA grant job

Description

Set the user for the RACF userid/groupid in PWGAssid grant job in xKD2SAM DB2 job.

Required or optional

Required

Default value

%aguser%

Location where the parameter value is storedIn the PWGAssid member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

<value>;

In the Configuration Tool (ICAT)

This value cannot be updated using the Configuration Tool.

Batch parameter name

KD2_OMPE_GRANT_AGUSER

PARMGEN name

KD2_OMPE_GRANT_AGUSER

PARMGEN classification

OMPE

KD2_OMPE_GRANT_EXUSER

User ID/group ID for EXGP grant job

Description

Set the user for the RACF userid/groupid in EXGPssid grant job in xKD2SAM DB2 job.

Required or optional

Required

Default value

%exuser%

Location where the parameter value is storedIn the EXGPssid member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

<value>;

In the Configuration Tool (ICAT)

This value cannot be updated using the Configuration Tool.

Batch parameter name

KD2_OMPE_GRANT_EXUSER

PARMGEN name

KD2_OMPE_GRANT_EXUSER

PARMGEN classification

OMPE

KD2_OMPE_GRANT_PEUSER

User ID/group ID for OMGP grant job

Description

Set the user for the RACF userid/groupid in OMGPssid grant job in xKD2SAM DB2 job.

Required or optional

Required

Default value

%peuser%

KD2_OMPE_GRANT_PWUSER

Location where the parameter value is stored

In the OMGPssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

<value>;

In the Configuration Tool (ICAT)

This value cannot be updated using the Configuration Tool.

Batch parameter name

KD2_OMPE_GRANT_PEUSER

PARMGEN name

KD2_OMPE_GRANT_PEUSER

PARMGEN classification

OMPE

KD2_OMPE_GRANT_PWUSER

User ID/group ID for PWG2 grant job

Description

Set the user for the RACF userid/groupid in PWG2ssid grant job in xKD2SAM DB2 job.

Required or optional

Required

Default value

%pwuser%

Location where the parameter value is stored

In the PWG2ssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

<value>;

In the Configuration Tool (ICAT)

This value cannot be updated using the Configuration Tool.

Batch parameter name

KD2_OMPE_GRANT_PWUSER

PARMGEN name

KD2_OMPE_GRANT_PWUSER

PARMGEN classification

OMPE

KD2_OMPE_ISPF_LANGUAGE

ISPF language information

Description

Used to specify the ISPF language. The default is ENU.

Required or optional

Required

Default value

ENU

Permissible values

ENU

Location where the parameter value is stored

In the FPEJINIT member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
language = "<value>";
```

In the Configuration Tool (ICAT)**Panel name**

ISPF Monitoring Dialogs

Panel ID

KD261PH

Panel field

ISPF language

Default value

ENU

Permissible values

ENU

Batch parameter name

KD2_OMPE_ISPF_LANG

PARMGEN name

KD2_OMPE_ISPF_LANGUAGE

PARMGEN classification

OMPE

KD2_OMPE_LOGSPACE

Logspace shortage

Description

Used to specify whether log space shortage events data collection is started.

Required or optional

Optional (Required in case KD2_OMPE_DB2_EVENT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is storedIn the OPPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

EVENTLOGSPACE=<value>

In the Configuration Tool (ICAT)**Panel name**

DB2 Event Exception Processing

Panel ID

KD261PG

Panel field

Logspace shortage

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_OMPE_LOGSPACE

KD2_OMPE_MAX_SESSIONS

PARMGEN name

KD2_OMPE_LOGSPACE

PARMGEN classification

OMPE

KD2_OMPE_MAX_SESSIONS

Maximum number of sessions

Description

Used to define the limit of simultaneous PE Client sessions. The specified value is an integer in the range from 0 to 500.

Required or optional

Optional (Required in case KD2_OMPE_PE_SUPPORT is set to Y)

Default value

99

Minimum

10

Maximum

500

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

MAXSESSION=<value>

In the Configuration Tool (ICAT)

Panel name

Workstation Interface Support

Panel ID

KD261PC

Panel field

Maximum number of sessions

Default value

99

Minimum

10

Maximum

500

Batch parameter name

KD2_OMPE_MAX_SESSIONS

PARMGEN name

KD2_OMPE_MAX_SESSIONS

PARMGEN classification

OMPE

KD2_OMPE_MGMTCLAS

Management Class for non-VSAM

Description

Used to specify a management class used for the allocation of all non-VSAM data sets created by the OMEGAMON Collector.

Required or optional

Optional

Default value

%RTE_SMS_MGMTCLAS%

Locations where the parameter value is stored**Location 1**In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

VDATASERVERMGMTCLAS= '<value>V'

Location 2In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

DATASERVERMGMTCLAS= '<value>'

In the Configuration Tool (ICAT)**Panel name**

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

Mgmtclas

Default value

&RTESMGT

Batch parameter name

KD2_OMPE_MGMTCLAS

PARMGEN name

KD2_OMPE_MGMTCLAS

PARMGEN classification

OMPE

KD2_OMPE_PE_SUPPORT

Enable PE Client support

Description

Used to specify whether the Performance Expert Client support is to be configured. Specify one of the following values:

Y

The Performance Expert Client support is enabled

N

The Performance Expert Client support is disabled.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is storedIn the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

TCPIP=<value>

KD2_OMPE_RUNALLOC

In the Configuration Tool (ICAT)

Panel name

Workstation Interface Support

Panel ID

KD261PC

Panel field

Enable Performance Expert Client support

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_OMPE_PE_SUPPORT

PARMGEN name

KD2_OMPE_PE_SUPPORT

PARMGEN classification

OMPE

KD2_OMPE_RUNALLOC

Automatic submit of allocation job

Description

Specify whether the 'Create DB2 related runtime members' job should trigger that the 'Allocate runtime datasets' job is submitted. The data set allocation job takes care of allocating all operational data sets required for the enabled functions, for example to collect data for Near-Term History. This job does not overwrite existing operational data sets.

Required or optional

Required

Default value

Y

Permissible values

Y, N

Locations where the parameter value is stored**Location 1**

In the CRTDB2 member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

<value> +

Location 2

In the CRTDB2M member of the *rhilev.midlev.rtename.RKD2PRF* library

Output line

<value> +

In the Configuration Tool (ICAT)

Panel name

Global Control Parameters

Panel ID

KD261PI

Panel field

Automatic submit of runtime dataset allocation job

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_OMPE_RUNALLOC

PARMGEN name

KD2_OMPE_RUNALLOC

PARMGEN classification

OMPE

KD2_OMPE_SHARED_PROFILE_LIB

HLQ for the shared profile library

Description

Specify the high-level qualifier of the RTE that you decided to use as the model for this RTE consisting of the High-level qualifier and the name of the model RTE. This parameter is only used if you set 'Use model definitions in this RTE' to Y. In this case all runtime members needed for this RTE are created on the basis of the profile library RKD2PRF library of the model RTE. For this RKD2PRF library you specify the high-level qualifier here.

Required or optional

Optional (Required in case KD2_OMPE_USE_MODEL is set to Y)

Default value

None

Location where the parameter value is storedIn the CRTDB2 member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

<value> +

In the Configuration Tool (ICAT)**Panel name**

Global Control Parameters

Panel ID

KD261PI

Panel field

HLQ of the shared profile library

Default value

None

Batch parameter name

KD2_OMPE_SHRD_PRFLIB

PARMGEN name

KD2_OMPE_SHARED_PROFILE_LIB

PARMGEN classification

OMPE

KD2_OMPE_STOCLAS

Storage Class for non-VSAM

Description

Used to specify a storage class used for the allocation of all non-VSAM data sets created by the OMEGAMON Collector.

KD2_OMPE_SUB_D2PADASP

Required or optional

Optional

Default value

%RTE_SMS_STORCLAS%

Locations where the parameter value is stored

Location 1

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

VDATASERVERSTORCLAS= '<value>V'

Location 2

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

DATASERVERSTORCLAS= '<value>'

In the Configuration Tool (ICAT)

Panel name

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

Storclas

Default value

&RTESTOR

Batch parameter name

KD2_OMPE_STOCLAS

PARMGEN name

KD2_OMPE_STOCLAS

PARMGEN classification

OMPE

KD2_OMPE_SUB_D2PADASP

OMPE/XCF Data Space Size DSPSIZE

Description

Defines the size in megabytes of the OMPE/XCF member data space. The data space is used by the OMPE/XCF component to hold the response data received from other members of the same LPAR or remote LPAR. Specify a size in multiples of 128M for up to a maximum of 2048M.

Required or optional

Required

Default value

128

Minimum

128

Maximum

2048

Location where the parameter value is stored

In the OMPE00 member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

DSPSIZE=<value>.M

In the Configuration Tool (ICAT)**Panel name**

OMEGAMON Collector Subsystem Information

Panel ID

KD261PA

Panel field

OMPE/XCF Data Space Size

Default value

128

Minimum

128

Maximum

2048

Batch parameter name

KD2_OMPE_SUB_D2PADASP

PARMGEN name

KD2_OMPE_SUB_D2PADASP

PARMGEN classification

DB2

KD2_OMPE_SUB_D2PAGRPN

OMPE/XCF Group name XCFGROUP

Description

Defines the default cross-coupling facility XCF group name. This group name is used by the OMPE subsystem to initialize the OMPE/XCF environment used by the OMPE Collector subsystem. You can specify any name in the range of 1 to 8 characters. The specified name must conform to XCF group naming standards.

When the XCF group name has a prefix of OMPE it is internally change to O5PE. To prevent the rename, specify a different 4 to 5-character prefix. For example: OMEGAXCF for all OMPE Collectors that communicate via the XCF gateway with one another.

Required or optional

Required

Default value

OMPEXCF

Location where the parameter value is storedIn the OMPE00 member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

XCFGROUP=<value>

In the Configuration Tool (ICAT)**Panel name**

OMEGAMON Collector Subsystem Information

Panel ID

KD261PA

Panel field

OMPE/XCF Group name

Default value

OMPEXCF

KD2_OMPE_SUB_D2PARCVT

Batch parameter name

KD2_OMPE_SUB_D2PAGRPN

PARMGEN name

KD2_OMPE_SUB_D2PAGRPN

PARMGEN classification

DB2

KD2_OMPE_SUB_D2PARCVT

OMPE/XCF Receive Tasks XCFTASKS

Description

Defines the number of XCF receive tasks that are to be attached as subtasks of the OMPE/XCF component task. These tasks are used by the OMPE/XCF component to process data receive requests from other members of the specified OMPE/XCF group. You can specify a number in the range of 02 to 16.

Required or optional

Required

Default value

6

Minimum

2

Maximum

16

Location where the parameter value is stored

In the OMPE00 member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

XCFTASKS=<value>

In the Configuration Tool (ICAT)**Panel name**

OMEGAMON Collector Subsystem Information

Panel ID

KD261PA

Panel field

OMPE/XCF Data Space Size

Default value

6

Minimum

2

Maximum

16

Batch parameter name

KD2_OMPE_SUB_D2PARCVT

PARMGEN name

KD2_OMPE_SUB_D2PARCVT

PARMGEN classification

DB2

KD2_OMPE_SUB_D2PASSIT

SSI timer value SSITIMER

Description

Defines the subsystem interface SSI loop detection timer in seconds. You can specify a timer in the range of 1 to 99 seconds. This timer value is used by the OMPE subsystem timer services component to measure the elapsed time an SSI function routine EOT, EOM, CMD, WTO executes. When the specified timer value is exceeded, the SSI broadcast function is abnormally terminated.

Required or optional

Required

Default value

30

Minimum

1

Maximum

99

Location where the parameter value is stored

In the OMPE00 member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SSITIMER=<value>

In the Configuration Tool (ICAT)

Panel name

OMEGAMON Collector Subsystem Information

Panel ID

KD261PA

Panel field

SSI timer value

Default value

30

Minimum

1

Maximum

99

Batch parameter name

KD2_OMPE_SUB_D2PASSIT

PARMGEN name

KD2_OMPE_SUB_D2PASSIT

PARMGEN classification

DB2

KD2_OMPE_SUB_D2PATSEC

OMPE TCMD Security Option

Description

Defines whether DB2 CANCEL THREAD command issued under user or task authority. If TCMDSECU=STC the CANCEL THREAD command will use the OMEGAMON started task authorization to issue the CANCEL command.

If TCMDSECU=USER the signed on user's authorization will be used.

KD2_OMPE_SUB_D2PAXCFT

Note: If the Classic security exit is not in use then the OMEGAMON started task authorization will always be used.

Required or optional

Required

Default value

STC

Permissible values

STC, USER

Location where the parameter value is stored

In the OMPEOPTS member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

TCMDSECU=<value>

In the Configuration Tool (ICAT)

Panel name

OMEGAMON Collector Subsystem Information

Panel ID

KD261PA

Panel field

OMPE TCMD Security Option

Default value

STC

Permissible values

STC, USER

Batch parameter name

KD2_OMPE_SUB_D2PATSEC

PARMGEN name

KD2_OMPE_SUB_D2PATSEC

PARMGEN classification

DB2

KD2_OMPE_SUB_D2PAXCFT

OMPE/XCF Timer Value XCFTIMER

Description

Defines the OMPE/XCF component SEND service request execution timer in seconds. You can specify a timer in the range of 01 to 99 seconds. This timer value is used by the OMPE/XCF component to measure the elapsed time a SEND service request executes. When the specified timer value is exceeded, the SEND service request is abnormally terminated.

Required or optional

Required

Default value

30

Minimum

1

Maximum

99

Location where the parameter value is stored

In the OMPE00 member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

XCFTIMER=<value>

In the Configuration Tool (ICAT)**Panel name**

OMEGAMON Collector Subsystem Information

Panel ID

KD261PA

Panel field

OMPE/XCF Timer value

Default value

30

Minimum

1

Maximum

99

Batch parameter name

KD2_OMPE_SUB_D2PAXCFT

PARMGEN name

KD2_OMPE_SUB_D2PAXCFT

PARMGEN classification

DB2

KD2_OMPE_SYSAFF

Add JES2 JOBPARM SYSAFF to job

Description

Specify whether you want to have the JES2 JOBPARM SYSAFF added to the generated DB2 related jobs. These jobs perform BIND or GRANT SQL statements on a specific DB2 subsystem and therefore have to be executed on the z/OS system where the respective DB2 subsystem runs on. This can be useful, for example if you want to install OMEGAMON XE for DB2 PE on several LPARs with shared DASD. See the Configuration and Customization Guide for details on different rollout scenarios. Furthermore if you set 'Use as model RTE for several LPARs' to 'Y' then the SYSAFF JOBPARM is also added to the 'Create DB2 related runtime members DB2 related' job.

Required or optional

Required

Default value

N

Permissible values

Y, N

Locations where the parameter value is stored**Location 1**In the CRTDB2 member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

<value> +

Location 2In the CRTDB2M member of the *rhilev.midlev.rtename.RKD2PRF* library**Output line**

<value> +

KD2_OMPE_TCPIP_ADDRESS

In the Configuration Tool (ICAT)

Panel name

Global Control Parameters

Panel ID

KD261PI

Panel field

Add JES2 JOBPARM sysaff to jobs

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_OMPE_SYSAFF

PARMGEN name

KD2_OMPE_SYSAFF

PARMGEN classification

OMPE

KD2_OMPE_TCPIP_ADDRESS

IP address

Description

Used to specify the IP address for OMEGAMON XE for DB2 PE to accept incoming requests. An IP host can have several IP addresses. In IP terms, such a host is called a multi homed host. To accept incoming requests on all available network interfaces, you must set this value to zeros 0.0.0.0.

Required or optional

Optional (Required in case KD2_OMPE_E2E_MON_SPRT,KD2_OMPE_PE_SUPPORT is set to Y)

Default value

0.0.0.0

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

IPADDRESS=<value>

In the Configuration Tool (ICAT)

Panel name

Workstation Interface Support

Panel ID

KD261PC

Panel field

IP address

Default value

0.0.0.0

Batch parameter name

KD2_OMPE_TCPIP_ADDRESS

PARMGEN name

KD2_OMPE_TCPIP_ADDRESS

PARMGEN classification

TCP

KD2_OMPE_TCPIP_NAME

TCP/IP name

Description

Used to specify the name of the TCP/IP address space you want to connect to. The specified value must be one to eight characters.

Required or optional

Optional (Required in case KD2_OMPE_E2E_MON_SPRT,KD2_OMPE_PE_SUPPORT is set to Y)

Default value

TCPIP

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

TCPNAME=<value>

In the Configuration Tool (ICAT)

Panel name

Workstation Interface Support

Panel ID

KD261PC

Panel field

TCP/IP name

Default value

TCPIP

Batch parameter name

KD2_OMPE_TCPIP_NAME

PARMGEN name

KD2_OMPE_TCPIP_NAME

PARMGEN classification

TCP

KD2_OMPE_THREAD_COMMIT

Thread commit indoubt

Description

Used to specify whether Thread commit indoubt events data collection is started.

Required or optional

Optional (Required in case KD2_OMPE_DB2_EVENT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

EVENTDDF=<value>

In the Configuration Tool (ICAT)

Panel name

DB2 Event Exception Processing

KD2_OMPE_TIMEOUT

Panel ID

KD261PG

Panel field

Thread commit indoubt

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_OMPE_THREAD_COMMIT

PARMGEN name

KD2_OMPE_THREAD_COMMIT

PARMGEN classification

OMPE

KD2_OMPE_TIMEOUT

Timeout

Description

Used to specify whether timeout events data collection is started.

Required or optional

Optional (Required in case KD2_OMPE_DB2_EVENT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

EVENTTIMEOUT=<value>

In the Configuration Tool (ICAT)**Panel name**

DB2 Event Exception Processing

Panel ID

KD261PG

Panel field

Timeout

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_OMPE_TIMEOUT

PARMGEN name

KD2_OMPE_TIMEOUT

PARMGEN classification

OMPE

KD2_OMPE_TRACE_LEVEL

OMEGAMON Collector trace level

Description

Used to specify trace level for the OMEGAMON XE for DB2 PE internal traces. Specify an integer value in the range from 0 to 127. Trace level 0 means internal tracing is not performed.

Required or optional

Required

Default value

0

Minimum

0

Maximum

8191

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

TRACELEVEL=<value>

In the Configuration Tool (ICAT)

Panel name

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

OMEGAMON Collector trace level

Default value

0

Minimum

0

Maximum

8191

Batch parameter name

KD2_OMPE_TRACE_LEVEL

PARMGEN name

KD2_OMPE_TRACE_LEVEL

PARMGEN classification

OMPE

KD2_OMPE_UNIT

Unit for non-VSAM

Description

Used to specify the storage device that is to be used for all non-VSAM data sets created by the OMEGAMON Collector. This parameter is ignored, if OMEGAMON XE for DB2 PE runs on a system managed by SMS.

Since SMS can be implemented in different ways, the Configuration tool does not attempt to validate these parameters. The dataset allocation jobs will use all parameters that you enter.

Required or optional

Optional

KD2_OMPE_UR

Default value

%RTE_SMS_UNIT%

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

DATASERVERUNIT=' <value> '

In the Configuration Tool (ICAT)**Panel name**

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_OMPE_UNIT

PARMGEN name

KD2_OMPE_UNIT

PARMGEN classification

OMPE

KD2_OMPE_UR

Unit of recovery problem

Description

Used to specify whether unit of recovery events data is started.

Required or optional

Optional (Required in case KD2_OMPE_DB2_EVENT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

EVENTURPROBLEM=<value>

In the Configuration Tool (ICAT)**Panel name**

DB2 Event Exception Processing

Panel ID

KD261PG

Panel field

Unit of recovery problem

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_OMPE_UR

PARMGEN name

KD2_OMPE_UR

PARMGEN classification

OMPE

KD2_OMPE_USE_MODEL

Use model definitions in this RTE

Description

Specify whether you want to use the DB2 subsystem definitions that are configured in a model RTE 'Use this RTE as a as a model' is set to Y different from this RTE. In the model RTE all the DB2 subsystems are configured that you want to monitor with the OMEGAMON Collector running from this RTE. All the configuration information that you need for the DB2 subsystem related runtime members is created in the profile library RKD2PRF of the model RTE. By submitting the job CRTDB2 in rhilev.midlev.rtename.RKD2SAM all runtime members needed for this RTE are created on the basis of the RKD2PRF library of the model RTE. The CRTDB2 job is generated by the 'Create runtime members OMEGAMON Collector/UI' job.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)**Panel name**

Global Control Parameters

Panel ID

KD261PI

Panel field

Use model definitions in this RTE

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_OMPE_USE_MODEL

PARMGEN name

KD2_OMPE_USE_MODEL

PARMGEN classification

OMPE

KD2_OMPE_VOLUME

Volser for non-VSAM

Description

Used to specify a volume serial number that is used for all non-VSAM data sets created by the OMEGAMON Collector. This parameter is ignored, if OMEGAMON XE for DB2 PE runs on a system managed by SMS.

Since SMS can be implemented in different ways, the Configuration tool does not attempt to validate these parameters. The dataset allocation jobs will use all parameters that you enter.

Required or optional

Optional

Default value

%RTE_SMS_VOLUME%

Locations where the parameter value is stored

Location 1

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

VDATASERVERVOLUME= '<value>V'

Location 2

In the OMPEMSTR member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

DATASERVERVOLUME= '<value>'

In the Configuration Tool (ICAT)

Panel name

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

Volser

Default value

&RTEV

Batch parameter name

KD2_OMPE_VOLUME

PARMGEN name

KD2_OMPE_VOLUME

PARMGEN classification

OMPE

KD2_OMPE_VSAM_DSHLQ

Use the KD2_OMPE_VSAM_DSHLQ parameter to specify the high-level qualifier for the VSAM data sets that the thread history collector allocates.

Description

This parameter specifies the high-level qualifier for the VSAM data sets allocated by the OMEGAMON Collector.

The default value is generated from the high-level qualifier and the mid-level qualifier that you specified for your RTE.

This parameter is also the basis of the THRDDATASET() parameter in the RKD2PAR(COPT&dbid) for the Enhanced 3270UI thread history VSAM data sets.

Required or optional

Required

Default value

%RTE_VSAM_HILEV%.%RTE_NAME%

Locations where the parameter value is stored

Location 1

In the OMPEMSTR member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

VDATASERVERHLQ=<value>

Location 2

In the OMDDssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

DEFINE CLUSTER(NAME(<value>..%DB%.HISTORY) -

Location 3

In the OMDDssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

DELETE (<value>..%DB%.HISTORY) CLUSTER

PARMGEN name

KD2_OMPE_VSAM_DSHLQ

PARMGEN classification

OMPE

KD2_OMPE_VSAM_MGMTCLAS

Management Class for VSAM

Description

Used to specify a management class used for the allocation of all VSAM data sets created by the OMEGAMON Collector.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

VDATASERVERMGMTCLAS='<value>'

In the Configuration Tool (ICAT)

Panel name

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

Mgmtclas

Default value

&RTESVMGT

KD2_OMPE_VSAM_STOCLAS

Batch parameter name

KD2_OMPE_VSAM_MGMTCLAS

PARMGEN name

KD2_OMPE_VSAM_MGMTCLAS

PARMGEN classification

OMPE

KD2_OMPE_VSAM_STOCLAS

Storage Class for VSAM

Description

Used to specify a storage class used for the allocation of all VSAM data sets created by the OMEGAMON Collector.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

VDATASERVERSTORCLAS=' <value> '

In the Configuration Tool (ICAT)**Panel name**

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_OMPE_VSAM_STOCLAS

PARMGEN name

KD2_OMPE_VSAM_STOCLAS

PARMGEN classification

OMPE

KD2_OMPE_VSAM_VOLUME

Volser for VSAM working data sets

Description

Used to specify a volume serial number that is used for all VSAM data sets created by the OMEGAMON Collector. This parameter is ignored, if OMEGAMON XE for DB2 PE runs on a system managed by SMS. Since SMS can be implemented in different ways, the Configuration tool does not attempt to validate these parameters. The dataset allocation jobs will use all parameters that you enter.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Location where the parameter value is stored

In the OMPEMSTR member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

VDATASERVERVOLUME= '<value>'

In the Configuration Tool (ICAT)**Panel name**

OMEGAMON Collector Information

Panel ID

KD261PN

Panel field

Volser

Default value

&RTEVV

Batch parameter name

KD2_OMPE_VSAM_VOLUME

PARMGEN name

KD2_OMPE_VSAM_VOLUME

PARMGEN classification

OMPE

KD2_PFn_HIS_VSAM_MCLAS1

Management class for VSAM dataset 1

Description

If the VSAM datasets are SMS-managed, then specify the SMS Management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

MGMTCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

MGMTCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Mgmtclas

Default value

&RTESVMGT

KD2_PF_HIS_LOG1

Batch parameter name

KD2_PF_HIS_VSAM_MCLAS1

PARMGEN name

KD2_PFn_HIS_VSAM_MCLAS1

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_SCLAS1

Storage class for VSAM dataset 1

Description

If the VSAM datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

STORCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

STORCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_PF_HIS_VSAM_SCLAS1

PARMGEN name

KD2_PFn_HIS_VSAM_SCLAS1

PARMGEN classification

NTH

KD2_PFn_HIS_LOG1

VSAM log dataset 1

Description

Specify a name for the VSAM log dataset to be created. Specify at least two datasets to allow for log switching. The Near-Term History Data Collector will automatically switch to a free log dataset when

the current dataset is full. Near-Term History VSAM dataset names must be unique for each DB2 subsystem.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

%RTE_VSAM_HILEV%.%RTE_NAME%.%DB%.RKD2VS01

Locations where the parameter value is stored

Location 1

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

ENTRIES(' <value> ') -

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

(NAME(<value>) -

Location 3

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

<value>

Location 4

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

DEFINE CLUSTER(NAME(<value>) -

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P7

Panel field

VSAM log data set name

Default value

None

Batch parameter name

KD2_PF_HIS_LOG1

PARMGEN name

KD2_PFn_HIS_LOG1

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_VOLUME1

Volser for VSAM dataset 1

Description

Specify the volume serial numbers for the allocation of the VSAM datasets. If VSAM datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

Required or optional

Optional

KD2_PF_HIS_LOG1

Default value

%RTE_SMS_VSAM_VOLUME%

Locations where the parameter value is stored

Location 1

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P7

Panel field

Volser

Default value

&RTEVV

Batch parameter name

KD2_PF_HIS_VSAM_VOL1

PARMGEN name

KD2_PFn_HIS_VSAM_VOLUME1

PARMGEN classification

NTH

KD2_PFn_HIS_WHEN_AUTHID

Selection criteria AUTHID

Description

Specifies selection criteria based on AUTHID. For example, if AUTH1 and AUTH2 were specified for AUTHID, only data for threads with the specified authorization identifiers would be collected.

To specify selection criteria, you can use the wildcard character *, which is for one or more characters, the suffix only, and the ?, which is for a single character.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

None

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

AUTH(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P8

Panel field

AUTHID

Default value

None

Batch parameter name

KD2_PF_HIS_WHEN_AUTHID

PARMGEN name

KD2_PFnn_HIS_WHEN_AUTHID

PARMGEN classification

NTH

KD2_PFnn_HIS_BUFSIZE

Data collection buffer size

Description

Specifies the parameter that controls the size of the buffer, which is used to hold IFI records until they can be written out to the log dataset by the Near-Term History Data Collector. This value is specified in kilobytes.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

1024

Minimum

50

Maximum

9999

Location where the parameter value is storedIn the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

BUFSIZE(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

Buffer size

Default value

1024

Minimum

50

Maximum

9999

Batch parameter name

KD2_PF_HIS_BUFSIZE

PARMGEN name

KD2_PFnn_HIS_BUFSIZE

PARMGEN classification

NTH

KD2_PFnn_HIS_WHEN_CONNID

Selection criteria CONNID

Description

Specifies selection criteria based on CONNID. For example, if CON01 and CON02 were specified for CONNID, only data for threads that use the specified connections would be collected.

To specify selection criteria, you can use the wildcard character *, which is for one or more characters, the suffix only, and the ?, which is for a single character.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

None

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

CONN(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P8

Panel field

CONNID

Default value

None

Batch parameter name

KD2_PF_HIS_WHEN_CONNID

PARMGEN name

KD2_PFnn_HIS_WHEN_CONNID

PARMGEN classification

NTH

KD2_PFnn_HIS_WHEN_CORRID

Selection criteria CORRID

Description

Specifies selection criteria based on CORRID. For example, if STC01 and STC02 were specified for CORRID, only data for threads with the specified correlation identifiers would be collected. To specify selection criteria, you can use the wildcard character *, which is for one or more characters, the suffix only, and the ?, which is for a single character.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

None

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

CORR(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

CORRID

Default value

None

Batch parameter name

KD2_PF_HIS_WHEN_CORRID

PARMGEN name

KD2_PFn_HIS_WHEN_CORRID

PARMGEN classification

NTH

KD2_PFn_HIS_COLL_INTV

Collection interval

Description

Specifies the time interval for statistics data collection. This interval also applies to thread data collection if grouping is selected. The default interval is the same as the RMF interval if RMF is active, or 15 minutes if RMF is not active.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

15

Location where the parameter value is storedIn the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

INTERVAL(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

Collection interval

Default value

15

Batch parameter name

KD2_PF_HIS_COLL_INTV

PARMGEN name

KD2_PFn_HIS_COLL_INTV

PARMGEN classification

NTH

KD2_PFnn_HIS_SUBINT

Collection sub-interval

Description

Specifies the number of minutes or seconds to be used as the smallest time grouping for display of historical thread accounting data. The sub-interval should be specified as a period of time for convenient display of the threads executed. The more threads are executed per minute the smaller the sub-interval that you may want to specify.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

5

Minimum

1

Maximum

60

Locations where the parameter value is stored

Location 1

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

NTAINTERVAL(<value>.S)

Location 2

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

NTAINTERVAL(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P8

Panel field

Collection sub-interval

Default value

5

Minimum

1

Maximum

60

Batch parameter name

KD2_PF_HIS_SUBINT

PARMGEN name

KD2_PFnn_HIS_SUBINT

PARMGEN classification

NTH

KD2_PFnn_HIS_SUBINT_UNIT

Collection sub-interval time unit

Description

Specifies the collection sub-interval time unit to be used to display the historical thread accounting data. Specify M for minutes or S for seconds.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

M

Permissible values

M, S

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P8

Panel field

Collection sub-interval unit

Default value

M

Permissible values

M, S

Batch parameter name

KD2_PF_HIS_SUBINT_UNIT

PARMGEN name

KD2_PFnn_HIS_SUBINT_UNIT

PARMGEN classification

NTH

KD2_PFnn_HIS_IFIREAD

IFI trace read frequency

Description

Specifies the IFI trace record read time in "mmssth" format where "mmssth" is minutes, seconds, tenths and hundredths of seconds. This parameter controls the frequency with which the Near-Term History Data Collector reads the new IFI trace records into the collection buffer.

You can increase the frequency by decreasing the interval, however, CPU utilization will increase. The default is 010000 which is 1 minute.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

010000

Minimum

000100

Maximum

010000

KD2_PF_HIS_IFIREAD

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

IFIREADTIME(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P8

Panel field

IFI read frequency

Default value

010000

Minimum

000100

Maximum

010000

Batch parameter name

KD2_PF_HIS_IFIREAD

PARMGEN name

KD2_PFnn_HIS_IFIREAD

PARMGEN classification

NTH

KD2_PFnn_HIS_WHEN_ORIG

Selection criteria ORIGAUTHID

Description

Specifies selection criteria based on ORIGAUTHID. To specify selection criteria, you can use the wildcard character *, which is for one or more characters, the suffix only, and the ?, which is for a single character.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

None

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

ORIGAUTH(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P8

Panel field

ORIGAUTHID

Default value

None

Batch parameter name

KD2_PF_HIS_WHEN_ORIG

PARMGEN name

KD2_PFn_HIS_WHEN_ORIG

PARMGEN classification

NTH

KD2_PFn_HIS_WHEN_PLAN

Selection criteria PLANNAME

Description

Specifies selection criteria based on PLANNAME. For example, if CICSPR01 and CICSPR02 were specified for PLANNAME, only data for threads with the specified plannames would be collected.

To specify selection criteria, you can use the wildcard character *, which is for one or more characters, the suffix only, and the ?, which is for a single character.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

None

Location where the parameter value is storedIn the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

PLAN(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

PLANNAME

Default value

None

Batch parameter name

KD2_PF_HIS_WHEN_PLAN

PARMGEN name

KD2_PFn_HIS_WHEN_PLAN

PARMGEN classification

NTH

KD2_PFn_HIS_SUSPCOLL

Suspend data collection

Description

Specifies the option that controls memory usage by the Near-Term History Data Collector during times when no VSAM dataset is available. A VSAM file is considered unavailable from the time all allocated file space is used until the end of a successful flush job execution. The 'Y' option causes the collector to discard the collected trace data until a VSAM file becomes available for use. The 'N' option causes the Near-Term History Data Collector to accumulate trace data to memory until a VSAM file becomes available for use.

KD2_PF_HIS_POSTPCT

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

Y

Permissible values

Y, N

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

SUSPCOLL(<value>Y)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P8

Panel field

Suspend data collection

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_PF_HIS_SUSPCOLL

PARMGEN name

KD2_PFn_HIS_SUSPCOLL

PARMGEN classification

NTH

KD2_PFn_HIS_POSTPCT

Threshold for historical collection

Description

Specifies the option to tune the Near-Term History Data Collector if you often see the DSNW133I messages issued by DB2. This value is used to compute a "high water mark" or threshold for historical collection. This threshold is a percentage of the total number of bytes in the IFI buffer. When this threshold is exceeded, DB2 will post the Near-Term History Data Collector to drain the buffer. The Near-Term History Data Collector will allow any percentage value from 1-99. Start from the default value of 70 and test small increments up or down.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

70

Minimum

1

Maximum

99

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

POSTPCT(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

Threshold

Default value

70

Minimum

1

Maximum

99

Batch parameter name

KD2_PF_HIS_POSTPCT

PARMGEN name

KD2_PFnn_HIS_POSTPCT

PARMGEN classification

NTH

KD2_PFnn_HIS_NEQSQL

Negative SQL option

Description

Specifies whether or not the number of SQL calls executed by a thread which resulted in a negative return code is collected. If Y is entered, the collector activates IFCIDs 58,59,60,61,62,64,65 and 66 to the DB2 START TRACE PERFORMANCE command.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is storedIn the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

NEGSQL (<value>Y)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PB

Panel field

Negative SQL

Default value

N

Permissible values

Y, N

KD2_PF_HIS_NEQSQL

Batch parameter name

KD2_PF_HIS_NEQSQL

PARMGEN name

KD2_PFn_HIS_NEQSQL

PARMGEN classification

NTH

KD2_PFn_HIS_DB2_STAT

Collect statistics data

Description

This specifies whether to collect statistics information IFCIDs 1 and 2.

If Y is entered, statistics information is recorded once for each collection interval.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

Y

Permissible values

Y, N

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

STATISTICS(<value>Y)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PB

Panel field

Statistics

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_PF_HIS_DB2_STAT

PARMGEN name

KD2_PFn_HIS_DB2_STAT

PARMGEN classification

NTH

KD2_PFn_HIS_START

Start Near-Term History

Description

Controls whether Near-Term History is to be configured and automatically started at Server startup.

Y

Configure and autostart Near-Term History.

C

Configure, but do not autostart Near-Term History. All required configuration members are generated and datasets are allocated. Near-Term History can be started via operator commands later. See Configuration and Customization Guide.

N

Near-Term History is not configured and as result cannot be started via operator command.

Required or optional

Required

Default value

N

Permissible values

Y, N, C

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PX

Panel field

Start Near-Term History

Default value

N

Permissible values

Y, N, C

Batch parameter name

KD2_PF_HIS_START

PARMGEN name

KD2_PFn_HIS_START

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_UNIT1

Unit for sequential dataset 1

Description

Specify the unit name for the allocation of the historical sequential datasets. If the historical sequential datasets are not SMS-managed then this is a required entry. If your installation does not use the unit name, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_UNIT%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.middle.rtename.RKD2SAM* library

Output line

UNIT(<value>) +

KD2_PF_HIS_DYN_MCLAS

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ1

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_PF_HIS_SEQ_UNIT1

PARMGEN name

KD2_PFn_HIS_SEQ_UNIT1

PARMGEN classification

NTH

KD2_PFn_HIS_DYN_MCLAS

Management class DYNAMIC

Description

If the historical sequential datasets are SMS-managed, then specify the SMS management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

MGMTCLAS(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ2

Panel field

Mgmtclas

Default value

&RTESVMGT

Batch parameter name

KD2_PF_HIS_DYN_MCLAS

PARMGEN name

KD2_PFn_HIS_DYN_MCLAS

PARMGEN classification

NTH

KD2_PFnn_HIS_DYN_SCLAS

Storage class DYNAMIC

Description

If the historical sequential datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

STORCLAS(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ2

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_PF_HIS_DYN_SCLAS

PARMGEN name

KD2_PFnn_HIS_DYN_SCLAS

PARMGEN classification

NTH

KD2_PFnn_HIS_DYN_UNIT

Unit DYNAMIC

Description

Specify the unit name for the allocation of the historical sequential datasets. If the historical sequential datasets are not SMS-managed then this is a required entry. If your installation does not use the unit name, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_UNIT%

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

UNIT(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

KD2_PF_HIS_DYN_VOLUME

Panel ID

KD261PZ2

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_PF_HIS_DYN_UNIT

PARMGEN name

KD2_PFnn_HIS_DYN_UNIT

PARMGEN classification

NTH

KD2_PFnn_HIS_DYN_VOLUME

Volser DYNAMIC

Description

Specify the volume serial numbers for the allocation of the historical sequential datasets. If the historical sequential datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

VOLSER(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ2

Panel field

Volser

Default value

&RTEVV

Batch parameter name

KD2_PF_HIS_DYN_VOL

PARMGEN name

KD2_PFnn_HIS_DYN_VOLUME

PARMGEN classification

NTH

KD2_PFnn_HIS_GDG_DSNAME

Dataset name GDG

Description

Specify the name for the base dataset of the Generation Data Group GDG. For the GDG type, the dataset name can have a maximum of 35 characters. And the storage mechanism is GDG.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to C,Y and KD2_PF_HIS_SEQ_TYP is set to G)

Default value

None

Locations where the parameter value is stored

Location 1

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

(NAME ('<value>')) -

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

ENTRIES('<value>') -

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ3

Panel field

Dataset name

Default value

None

Batch parameter name

KD2_PF_HIS_GDG_DSNAME

PARMGEN name

KD2_PFnn_HIS_GDG_DSNAME

PARMGEN classification

NTH

KD2_PFnn_HIS_GDG_MCLAS

Management class GDG

Description

If the historical sequential datasets are SMS-managed, then specify the SMS management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

KD2_PF_HIS_GDG_SCLAS

Output line

MGMTCLAS(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ3

Panel field

Mgmtclas

Default value

&RTESVMGT

Batch parameter name

KD2_PF_HIS_GDG_MCLAS

PARMGEN name

KD2_PFn_HIS_GDG_MCLAS

PARMGEN classification

NTH

KD2_PFn_HIS_GDG_SCLAS

Storage class GDG

Description

If the historical sequential datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

STORCLAS(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ3

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_PF_HIS_GDG_SCLAS

PARMGEN name

KD2_PFn_HIS_GDG_SCLAS

PARMGEN classification

NTH

KD2_PFnn_HIS_GDG_UNIT

Unit GDG

Description

Specify the unit name for the allocation of the historical sequential datasets. If the historical sequential datasets are not SMS-managed then this is a required entry. If your installation does not use the unit name, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_UNIT%

Locations where the parameter value is stored

Location 1

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

UNIT(<value>)

Location 2

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

UNIT(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ3

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_PF_HIS_GDG_UNIT

PARMGEN name

KD2_PFnn_HIS_GDG_UNIT

PARMGEN classification

NTH

KD2_PFnn_HIS_GDG_VOLUME

Volser GDG

Description

Specify the volume serial numbers for the allocation of the historical sequential datasets. If the historical sequential datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

VOLUME(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ3

Panel field

Volser

Default value

&RTEVV

Batch parameter name

KD2_PF_HIS_GDG_VOL

PARMGEN name

KD2_PFnn_HIS_GDG_VOLUME

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQ_ARC_GDGLIM

GDG Limit for the archive dataset

Description

Specify the number of GDG generations to be used for this GDG. You can specify 1 to 255.

This field is only applicable if you specified GDG as the storage mechanism to be used for archiving.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to C,Y and KD2_PF_HIS_SEQ_TYP is set to S and KD2_PF_HIS_SEQ_ARC_TYP is set to GDG)

Default value

7

Minimum

1

Maximum

255

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

LIMIT(<value>))

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZA

Panel field

Limit for GDG data sets

Default value

7

Minimum

1

Maximum

255

Batch parameter name

KD2_PF_HIS_SEQ_ARC_GDGLIM

PARMGEN name

KD2_PFnn_HIS_SEQ_ARC_GDGLIM

PARMGEN classification

NTH

KD2_PFnn_SQLID

SQLID

Description

Customize a different SQLID if other than the default USER in the following xKD2SAM DB2 Grant jobs:

- EXGPssid
- EXGRssid
- OMGPssid: Grant DB2 privileges to each user ID that will work with the OMEGAMON Server
- OMGRssid: Grant DB2 privileges on the DB2 subsystem to the OMEGAMON Collector plan/package owner that are necessary to administer the collector

Required or optional

Required

Default value

USER

Locations where the parameter value is stored**Location 1**

In the EXGPssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
SET CURRENT SQLID = <value>;
```

Location 2

In the EXGRssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
SET CURRENT SQLID = <value>;
```

Location 3

In the OMGPssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
SET CURRENT SQLID = <value>;
```

Location 4

In the OMGRssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
SET CURRENT SQLID = <value>;
```

In the Configuration Tool (ICAT)

This value cannot be updated using the Configuration Tool.

Batch parameter name

KD2_PF_SQLID

PARMGEN name

KD2_Pfnn_SQLID

PARMGEN classification

OMPE

KD2_PLAN_NAME_OVERRIDE

Customize DB2 plan names

Description

Customize a different DB2 plan name if you want to override the internal DB2 plan name PLAN(DSNTIAvv) in the following Bind/Grant-type xKD2SAM DB2 jobs: (where vv = 1:2 digits of ssid)

- EXCQssid
- EXCTssid
- EXCVssid
- EXC0ssid
- EXC1ssid
- EXC2ssid
- EXC3ssid
- EXC8ssid
- EXDVssid
- EXGPssid
- EXGRssid
- OMGPssid
- OMGRssid
- PWGAssid
- PWG1ssid
- PWG2ssid

Required or optional

Required

Default value

None

Locations where the parameter value is stored**Location 1**

In the EXCQssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -
```

Location 2

In the EXCTssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -
```

Location 3

In the EXCVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -
```

Location 4

In the EXCOssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -
```

Location 5

In the EXC1ssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -
```

Location 6

In the EXC2ssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -
```

Location 7

In the EXC3ssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -
```

Location 8

In the EXC8ssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -
```

Location 9

In the EXDVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -
```

Location 10

In the EXGPssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -
```

Location 11

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -
```

Location 12

In the OMGPssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -

Location 13

In the OMGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -

Location 14

In the PWGAssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -

Location 15

In the PWG1ssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -

Location 16

In the PWG2ssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

RUN PROGRAM(<value>) PLAN(%KD2_I_DB2_PLAN%) -

In the Configuration Tool (ICAT)

This value cannot be updated using the Configuration Tool.

Batch parameter name

KD2_PLAN_NAME_OVERRIDE

PARMGEN name

KD2_PLAN_NAME_OVERRIDE

PARMGEN classification

OMPE

Chapter 3. Profile parameters

This section lists the profile parameters.

Monitoring profiles specify which monitoring functionality is to be used for the different DB2 subsystems. Each DB2 subsystem is associated with a monitoring profile.

OMEGAMON for Db2 PE offers many functions that can be configured for each DB2 subsystem. In most cases, however, the monitoring requirements for the different DB2 subsystems are not completely unique, which means that you can reuse one configuration for several DB2 subsystems. For example, in a development environment you might want to collect very detailed performance data to perform a sophisticated analysis, while in a production environment, this level of detail is not needed and causes unnecessary overhead. So you would use one set of configuration values for the DB2 subsystems that are used for development and another set of configuration values for DB2 subsystems in production.

A monitoring profile is such a set of configuration values. It is independent of the DB2 subsystem. Each DB2 subsystem is associated with a monitoring profile to determine the monitoring functionality. Several DB2 subsystems can be associated with the same profile, independent of the LPAR they reside on. As a result, profiles are reusable for many different DB2 subsystems that have similar monitoring requirements across different LPARs, and you can do changes to monitoring profiles rather than reconfiguring every single DB2 subsystem.

As the runtime members for a DB2 subsystem depend on the configuration values of the monitoring profile as well as the configuration values of the DB2 subsystem itself, the creation of the runtime members requires two steps. The first step creates the profile members, where all values that are specific to the DB2 subsystem are substituted by variables, and writes them to *&rhilev.&rte.RKD2PRF*. The second step replaces these variables with the actual configuration values of the DB2 subsystem and writes the members to *&rhilev.&rte.RKD2SAM* and *&rhilev.&rte.RKD2PAR*.

How to create DB2 profiles in PARMGEN user profiles

This section explains how to create DB2 profiles in PARMGEN user profiles.

DB2 profiles are configured along all other configuration parameters in the PARMGEN user profile. They are identified by **KD2_PFxx** where *xx* is the number that distinguishes different DB2 profiles. For example, **KD2_PF01** refers to the first DB2 profile and **KD2_PF02** refers to the second DB2 profile. You can create up to 99 DB2 profiles.

The section that holds DB2 profiles is structured as follows:

```
KD2_PF          BEGIN

KD2_PFxx_ROW    xx
KD2_PFxx_PROFID P0xx
KD2_PFxx_DESCRIPTION "P0xx prof"
...

KD2_PFyy_ROW    yy
KD2_PFyy_PROFID P0yy
KD2_PFyy_DESCRIPTION "P0yy prof"
...

KD2_PF          END
```

where *xx* and *yy* are the numbers of those two DB2 profiles. The parameter **KD2_PFxx_PROFID** contains the ID that is used to assign a DB2 subsystem configuration with a DB2 profile. You can choose your ID as you like but it is recommended to include the number that identifies the DB2 profile in the ID in order to easily identify the relationship between DB2 subsystems and DB2 profiles.

In order to assign a DB2 profile to a DB2 subsystem configuration, use the parameter **KD2_DBzz_DB2_PROFID**. For example, to assign the DB2 profile **P0xx** to a DB2 subsystem configuration set, use the following parameter:

KD2_DBzz_DB2_PROFID	P0xx
---------------------	------

Object/Volume analysis

This section lists the parameters for object or volume analysis.

Object analysis provides information about DB2 object allocations, object activities, volume activities, and data set extend activities.

You can start object analysis in one of the following ways:

- Manually, using the START OBJECT ANALYSIS COLLECTORS panel.

Note: If there are significant levels of I/O activity on monitored DASD volumes in your environment, you can start this function manually to measure specific workloads or help manage isolated performance situations.

- Automatically, when the OMEGAMON for Db2 PE server is activated.

Note: It is recommended that you do not automatically start object analysis in the AUTOSTART configuration.

By default, the Object Analysis function is shipped with a security level of 3, and requires that you enter a level 3 password to successfully complete the startup. If you want to use external security, you must have the appropriate resource class definition attached to your OMEGAMON for Db2 PE logon identifier.

Note: To start Object Analysis, you must first start OMEGAMON for Db2 PE Event Collection Manager (EVENTMGR).

OMEGAMON for Db2 PE provides object analysis data only for active DB2 objects.

Object analysis can only be performed on a single DB2 subsystem, no matter whether the subsystem is a member of a data sharing group or not.

KD2_PFnn_OA_ECM

Start Event collection manager

Description

The Event collection manager ECM provides an environment that is required for Object/Volume Analysis Collectors. The ECM does not cause much overhead. If you start the ECM at OMEGAMON Collector startup, then you can start Object/Volume Analysis from the Classic Interface later.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)

Panel name

Object and Volume Analysis

Panel ID

KD261PM

Panel field

Start the Event Collection Manager

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PFOA_ECM

PARMGEN name

KD2_PFnn_OA_ECM

PARMGEN classification

OBJ_ANAL

KD2_PFnn_OA_INTV

Object analysis collection info

Description

This specifies the time interval in minutes for the object analysis and the volume analysis collectors. The interval may be from 1 to 1440 minutes.

Required or optional

Optional (Required in case KD2_PFOA_START is set to Y)

Default value

15

Minimum

1

Maximum

1440

Location where the parameter value is stored

In the OMOAssid member of the *rhilev.midlev.rtename.RKD2PRF* library

Output line

F EVENTMGR,START DB2=%DB%,INTERVAL=<value>,THREAD=&THREAD

In the Configuration Tool (ICAT)**Panel name**

Object and Volume Analysis

Panel ID

KD261PM

Panel field

Object analysis collection interval

Default value

15

Minimum

1

Maximum

1440

Batch parameter name

KD2_PFOA_INTV

PARMGEN name

KD2_PFnn_OA_INTV

PARMGEN classification

OBJ_ANAL

KD2_PFn_OA_START

Start Object Analysis

Description

Specify Y if you want to start Object/Volume Analysis for DB2 subsystems associated with this profile at startup of the OMEGAMON Collector.

Note that Object/Volume Analysis causes considerable overhead. Object/Volume Analysis can be started as needed via operator commands later. See Configuration and Customization Guide for details.

Required or optional

Optional (Required in case KD2_PF_OA_ECM is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMOAssid member of the *rhilev.midlev.rtename.RKD2PRF* library

Output line

STARTOA=<value>

In the Configuration Tool (ICAT)

Panel name

Object and Volume Analysis

Panel ID

KD261PM

Panel field

Start Object/Volume Analysis

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_OA_START

PARMGEN name

KD2_PFn_OA_START

PARMGEN classification

OBJ_ANAL

KD2_PFn_OA_THREAD

DB2 objects thread info

Description

This indicates whether thread information will be collected during object analysis.

Required or optional

Optional (Required in case KD2_PF_OA_START is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMOAssid member of the *rhilev.midlev.rtename.RKD2PRF* library

Output line

F EVENTMGR,START DB2=%DB%,INTERVAL=&02EINT,THREAD=<value>

In the Configuration Tool (ICAT)**Panel name**

Object and Volume Analysis

Panel ID

KD261PM

Panel field

Thread information on DB2 objects

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_PFOA_THRD

PARMGEN name

KD2_PFnn_OA_THREAD

PARMGEN classification

OBJ_ANAL

KD2_PFnn_OA_WAIT

Wait interval

Description

The Event Collection Manager must be active before Object/Volume Analysis can be started for a DB2 subsystem. The wait interval specifies the number of seconds that have to pass after ECM startup before the startup commands for Object/Volume Analysis are issued.

ECM is started implicitly when you configure Object Analysis to be auto-started at Common collector startup. If you specified a wait interval greater than 0 in several monitoring profiles that are used the maximum wait interval specified is used.

Required or optional

Optional (Required in case KD2_PFOA_ECM is set to Y)

Default value

5

Minimum

0

Maximum

99

Location where the parameter value is stored

In the OMOAssid member of the *rhilev.midlev.rtename.RKD2PRF* library

Output line

WAIT=<value>

In the Configuration Tool (ICAT)**Panel name**

Object and Volume Analysis

Panel ID

KD261PM

Panel field

Wait interval

Default value

5

Minimum

0

Maximum

99

Batch parameter name

KD2_PFOA_WAIT

PARMGEN name

KD2_PFn_OA_WAIT

PARMGEN classification

OBJ_ANAL

Periodic exception processing

This section lists the parameters for periodic exception processing.

Periodic Exception Processing analyzes system metrics and compares them against predefined thresholds, user-defined thresholds, and application metrics.

When a threshold is exceeded, a periodic exception is shown. This event is commonly called an exception. This function is available in Performance Expert Client.

You can start periodic exception processing in one of the following ways:

- Manually, after you start Performance Expert Client. In this case, you can define a set of thresholds for each user ID.
- Automatically, to start one user's threshold definitions when the server starts. In this case, the threshold definitions are already started when the user logs on to the client.

KD2_PFn_AEXCP_D2PYACT

Enable Automatic Exception Processing

Description

Used to enable or disable Automatic Exception Processing.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)**Panel name**

Periodic Exception Processing

Panel ID

KD261PY

Panel field

Enable Periodic Exception Processing

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_Pf_AEXCP_D2PYACT

PARMGEN name

KD2_Pfnn_AEXCP_D2PYACT

PARMGEN classification

EXCP

KD2_Pfnn_AEXCP_D2TPFDSN

Exception file dataset name

Description

Used to specify the name of the DPMOUT output data set. Specify a fully qualified file data set name.

Required or optional

Optional (Required in case KD2_Pf_AEXCP_D2TPFFLG is set to Y)

Default value

None

Locations where the parameter value is stored**Location 1**

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

AUTOEXCPFILENAME=<value>

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

ENTRIES(' <value> ') -

Location 3

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

DSNAME(' <value> ') -

In the Configuration Tool (ICAT)**Panel name**

Periodic Exception Processing

Panel ID

KD261PY

Panel field

Exception file data set name

Default value

None

Batch parameter name

KD2_Pf_AEXCP_D2TPFDSN

PARMGEN name

KD2_Pfnn_AEXCP_D2TPFDSN

PARMGEN classification

EXCP

KD2_Pfnn_AEXCP_D2TPFDSP

Disposition for Exception file dataset

Description

Used to specify the disposition of the DPMOUT file data set. Valid values are MOD or OLD.

Required or optional

Optional (Required in case KD2_PF_AEXCP_D2TPFFLG is set to Y)

Default value

MOD

Permissible values

MOD, OLD

Locations where the parameter value is stored**Location 1**

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

AUTOEXCPCFILEDISP=<value>

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

<value> CATALOG -

In the Configuration Tool (ICAT)**Panel name**

Periodic Exception Processing

Panel ID

KD261PY

Panel field

Exception file data set DISP

Default value

MOD

Permissible values

MOD, OLD

Batch parameter name

KD2_PF_AEXCP_D2TPFDSP

PARMGEN name

KD2_PFnn_AEXCP_D2TPFDSP

PARMGEN classification

EXCP

KD2_PFnn_AEXCP_D2TPFFLG

Exception file

Description

Used to activate export of the performance data at time of exception to the exception file.

Required or optional

Optional (Required in case KD2_PF_AEXCP_D2PYACT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

AUTOEXCPCFILE=<value>

In the Configuration Tool (ICAT)

Panel name

Periodic Exception Processing

Panel ID

KD261PY

Panel field

Exception file

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_AEXCP_D2TPFFLG

PARMGEN name

KD2_PFnn_AEXCP_D2TPFFLG

PARMGEN classification

EXCP

KD2_PFnn_AEXCP_D2TPINTV

Periodic interval

Description

Used to specify the time period between exception checks in seconds. Specify an integer value in the range from 1 to 7200.

Required or optional

Optional (Required in case KD2_PF_AEXCP_D2PYACT is set to Y)

Default value

100

Minimum

1

Maximum

7200

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

AUTOEXCPPERIOD=<value>

In the Configuration Tool (ICAT)

Panel name

Periodic Exception Processing

Panel ID

KD261PY

Panel field

Periodic interval

Default value

100

Minimum

1

Maximum

7200

Batch parameter name

KD2_Pf_AEXCP_D2TPINTV

PARMGEN name

KD2_Pfnn_AEXCP_D2TPINTV

PARMGEN classification

EXCP

KD2_Pfnn_AEXCP_D2TPLDSN

Exception log dataset name

Description

Used to specify the name of the exception log data set. Specify a fully qualified data set name.

Required or optional

Optional (Required in case KD2_Pf_AEXCP_D2TPLFLG is set to Y)

Default value

None

Locations where the parameter value is stored**Location 1**

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

AUTOEXCPLOGNAME=<value>

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

DSNAME(' <value> ') -

Location 3

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

ENTRIES(' <value> ') -

In the Configuration Tool (ICAT)**Panel name**

Periodic Exception Processing

Panel ID

KD261PY

Panel field

Exception log data set name

Default value

None

Batch parameter name

KD2_Pf_AEXCP_D2TPLDSN

PARMGEN name

KD2_Pfnn_AEXCP_D2TPLDSN

PARMGEN classification

EXCP

KD2_Pfnn_AEXCP_D2TPLDSP

Disposition for Exception log dataset

Description

Used to specify the disposition of the exception log data set. Valid values are MOD or OLD.

Required or optional

Optional (Required in case KD2_PF_AEXCP_D2TPLFLG is set to Y)

Default value

MOD

Permissible values

MOD, OLD

Locations where the parameter value is stored**Location 1**

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

AUTOEXCPLOGDISP=<value>

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

<value> CATALOG -

In the Configuration Tool (ICAT)**Panel name**

Periodic Exception Processing

Panel ID

KD261PY

Panel field

Exception log data set DISP

Default value

MOD

Permissible values

MOD, OLD

Batch parameter name

KD2_PF_AEXCP_D2TPLDSP

PARMGEN name

KD2_PFnn_AEXCP_D2TPLDSP

PARMGEN classification

EXCP

KD2_PFnn_AEXCP_D2TPLFLG

Exception log

Description

Used to activate export of the exception data to the exception log.

Required or optional

Optional (Required in case KD2_PF_AEXCP_D2PYACT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

AUTOEXCPLOG=<value>

In the Configuration Tool (ICAT)

Panel name

Periodic Exception Processing

Panel ID

KD261PY

Panel field

Exception log

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_AEXCP_D2TPLFLG

PARMGEN name

KD2_PFnn_AEXCP_D2TPLFLG

PARMGEN classification

EXCP

KD2_PFnn_AEXCP_D2TPTDSN

Threshold data set name

Description

The Exception Threshold data set contains the exception thresholds for the Statistics and Accounting exception reports and traces. When exception processing is active, the instrumentation data is checked against these thresholds.

You can either use an existing threshold data set or let ICAT generate a new threshold data set. Specify a fully qualified data set name without quotes. If the specified threshold data set does not exist, ICAT generates an empty sequential data set using the following attributes:

RECFM

VB

LRECL

255

BLKSIZE

6233

You need to specify thresholds in the specified data set. If the threshold data set is empty, Automatic Exception Processing is not started and the following message is written to the message log:

```
FPEV0263E D823 AUTOMATIC EXCP NOT STARTED - NO VALID THRESHOLD
```

To specify thresholds:

Use the thresholds in the supplied sample Threshold data set DGOETV41 in RKO2DATA or in case of an SMP/E Sharing RTE: TKO2DATA. The sample contains a selection of exception fields with predefined threshold values and can be used to get started with exception reporting. To use the sample threshold data set as input for Automatic Exception Processing, copy the contents of DGOETV41 to the threshold data set generated by ICAT.

Note: The sample Exception Threshold data set member DGOETV41 has a different record length. As a result, when you copy member DGOETV41 to your newly allocated data set, you see a warning that records are truncated. You can ignore this warning.

Refer to the Reporting User's Guide 'Specifying exceptions using the Exception Threshold data set editor' and 'Exception Threshold data set' for additional information.

Required or optional

Optional (Required in case KD2_PF_AEXCP_D2PYACT is set to Y)

Default value

%RTE_HILEV%.%RTE_NAME%.RKD2THRS

Locations where the parameter value is stored**Location 1**

In the OMPESSID member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

AUTOEXCPTHNAME=<value>

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

DSNAME(' <value> ') -

Location 3

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

ENTRIES(' <value> ') -

In the Configuration Tool (ICAT)**Panel name**

Periodic Exception Processing

Panel ID

KD261PY

Panel field

Threshold data set name

Default value

None

Batch parameter name

KD2_PF_AEXCP_D2TPTDSN

PARMGEN name

KD2_PFnn_AEXCP_D2TPTDSN

PARMGEN classification

EXCP

KD2_PFnn_AEXCP_D2TPTFMC

Management Class of Exception datasets

Description

Used to specify the SMS management class for the Excp processing datasets that are to be allocated.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

MGMTCLAS(<value>) -

In the Configuration Tool (ICAT)**Panel name**

Periodic Exception Processing

Panel ID

KD261PY

Panel field

MGMTCLAS

Default value

None

Batch parameter name

KD2_Pf_AEXCP_D2TPTFMC

PARMGEN name

KD2_PFnn_AEXCP_D2TPTFMC

PARMGEN classification

EXCP

KD2_PFnn_AEXCP_D2TPTFSC

Storage Class of Exception datasets

Description

Used to specify the SMS storage class for the Excp processing datasets that are to be allocated.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Location where the parameter value is storedIn the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library**Output line**

STORCLAS(<value>) -

In the Configuration Tool (ICAT)**Panel name**

Periodic Exception Processing

Panel ID

KD261PY

Panel field

STORCLAS

Default value

None

Batch parameter name

KD2_Pf_AEXCP_D2TPTFSC

PARMGEN name

KD2_PFnn_AEXCP_D2TPTFSC

PARMGEN classification

EXCP

KD2_PFnn_AEXCP_D2TPUID

User ID

Description

Used to specify the user ID of the OMEGAMON XE for DB2 PE user for whom you want to start Automatic Exception Processing. The user ID can be up to 8 characters long. The default user ID is the OMEGAMON XE for DB2 PE user ID.

Required or optional

Optional (Required in case KD2_PF_AEXCP_D2PYACT is set to Y)

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

AUTOEXCPUSER=<value>

In the Configuration Tool (ICAT)**Panel name**

Periodic Exception Processing

Panel ID

KD261PY

Panel field

Threshold user ID

Default value

None

Batch parameter name

KD2_PF_AEXCP_D2TPUID

PARMGEN name

KD2_PFnn_AEXCP_D2TPUID

PARMGEN classification

EXCP

KD2_PFnn_AEXCP_D2TPUXIT

Use user exit

Description

Used to specify whether the user exit for Automatic Exception Processing is activated. The default is N.

Required or optional

Optional (Required in case KD2_PF_AEXCP_D2PYACT is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

AUTOEXCPEXIT=<value>

In the Configuration Tool (ICAT)**Panel name**

Periodic Exception Processing

Panel ID

KD261PY

Panel field

User exception exit

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_AEXCP_D2TPUXIT

PARMGEN name

KD2_PFnn_AEXCP_D2TPUXIT

PARMGEN classification

EXCP

KD2_PFnn_AEXCP_D2TPVL

Volser of Exception datasets

Description

Used to specify the volser for the Automatic Excp processing datasets that are to be allocated.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOL(<value>) -

In the Configuration Tool (ICAT)**Panel name**

Periodic Exception Processing

Panel ID

KD261PY

Panel field

Volser

Default value

None

Batch parameter name

KD2_PF_AEXCP_D2TPVL

PARMGEN name

KD2_PFnn_AEXCP_D2TPVL

PARMGEN classification

EXCP

Parameter Reference - thread history

This section lists the parameters added or updated for thread history. This includes several parameters introduced to support thread history in the Enhanced 3270 user interface.

Note: You can start thread history collection by default when you start OMEGAMON for Db2 PE, or you can use operator commands to start and stop thread history collection.

There are several new parameters introduced to support the Enhanced 3270UI thread history:

- KD2_PFnn_THRDHIS_LOG_NUM
- KD2_PFnn_THRDHIS_DYN_SQL
- KD2_PFnn_THRDHIS_LOCK_CNTN
- KD2_PFnn_THRDHIS_LOCK_SUSP

- KD2_PFn_THRDHIS_SCAN_SUMM
- KD2_PFn_THRDHIS_SORT_SUMM

Note: These parameters can be configured in PARMGEN, but they are not yet implemented for use with thread history in the Enhanced 3270UI.

Change to KD2_PFn_HIS_STORE parameter

The following field has the same default value but now has additional options that support thread history:

KD2_PFn_HIS_STORE now allows values with the THVSAM option (VSAMTHVSAM, VSAMSEQTHVSAM, SEQTHVSAM, THVSAM). This option activates Enhanced 3270UI thread history collection.

The following sections detail the parameters that have been updated to facilitate thread history in the Enhanced 3270UI.

KD2_OMPE_VSAM_DSHLQ

Use the KD2_OMPE_VSAM_DSHLQ parameter to specify the high-level qualifier for the VSAM data sets that the thread history collector allocates.

Description

This parameter specifies the high-level qualifier for the VSAM data sets allocated by the OMEGAMON Collector.

The default value is generated from the high-level qualifier and the mid-level qualifier that you specified for your RTE.

This parameter is also the basis of the THRDDATASET() parameter in the RKD2PAR(COPT&dbid) for the Enhanced 3270UI thread history VSAM data sets.

Required or optional

Required

Default value

%RTE_VSAM_HILEV%.%RTE_NAME%

Locations where the parameter value is stored

Location 1

In the OMPEMSTR member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

VDATASERVERHLQ=<value>

Location 2

In the OMDDssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

DEFINE CLUSTER(NAME(<value>..%DB%.HISTORY) -

Location 3

In the OMDDssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

DELETE (<value>..%DB%.HISTORY) CLUSTER

PARMGEN name

KD2_OMPE_VSAM_DSHLQ

PARMGEN classification

OMPE

KD2_PFnn_HIS_ACCTG_CLAS

Use the KD2_PFnn_HIS_ACCTG_CLAS parameter to specify one or more types of accounting data to collect.

Description

Specifies the type of accounting data to collect.

Class 1 IFCID 3 no In-DB2 or I/O and lock wait times.

Class 2 IFCID 3 In-DB2 time.

Class 3 IFCID 3 I/O and lock wait times.

Class 7 IFCID 3,239 Package/DBRM In-DB2 time.

Class 8 IFCID 3,239 Package/DBRM I/O and lock wait times.

Class 10 IFCID 239 Package detail

Class 11 IFCID 3,200 No package info. For DB2 v11 and above only.

Enter a list of the accounting classes that you want to collect data from. For example "1 2 3"

NOTE: In order to reduce the number of IFCIDs collected and not collect the IFCID 239, class 11 should be requested

without classes 7, 8 and 10. Class 11 supported in DB2 v11 and above.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

1

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

ACCTG(<value>Y)

PARMGEN name

KD2_PFnn_HIS_ACCTG_CLAS

PARMGEN classification

NTH

KD2_PFnn_HIS_BUFSIZE

Data collection buffer size

Description

Specifies the parameter that controls the size of the buffer, which is used to hold IFI records until they can be written out to the log dataset by the Near-Term History Data Collector. This value is specified in kilobytes.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

1024

Minimum

50

Maximum

9999

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

BUFSIZE(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

Buffer size

Default value

1024

Minimum

50

Maximum

9999

Batch parameter name

KD2_Pf_HIS_BUFSIZE

PARMGEN name

KD2_PFn_HIS_BUFSIZE

PARMGEN classification

NTH

KD2_PFn_HIS_COLL_INTV

Collection interval

Description

Specifies the time interval for statistics data collection. This interval also applies to thread data collection if grouping is selected. The default interval is the same as the RMF interval if RMF is active, or 15 minutes if RMF is not active.

Required or optional

Optional (Required in case KD2_Pf_HIS_START is set to Y)

Default value

15

Location where the parameter value is storedIn the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

INTERVAL(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

Collection interval

Default value

15

Batch parameter name

KD2_Pf_HIS_COLL_INTV

KD2_PFn_HIS_DYN_DSNAME

PARMGEN name

KD2_PFn_HIS_COLL_INTV

PARMGEN classification

NTH

KD2_PFn_HIS_DB2_STAT

Collect statistics data

Description

This specifies whether to collect statistics information IFCIDs 1 and 2.

If Y is entered, statistics information is recorded once for each collection interval.

Required or optional

Optional (Required in case KD2_PFn_HIS_START is set to Y)

Default value

Y

Permissible values

Y, N

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

STATISTICS(<value>Y)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PB

Panel field

Statistics

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_PFn_HIS_DB2_STAT

PARMGEN name

KD2_PFn_HIS_DB2_STAT

PARMGEN classification

NTH

KD2_PFn_HIS_DYN_DSNAME

This parameter lets you specify a base dataset name that is used to create the sequential datasets for storing Near-Term History trace data.

Description

Specify a base dataset name that is used to create the sequential datasets that store Near-Term History trace data. Use the following variables to construct the sequential dataset name. To ensure unique dataset names, you must use at least @DB2, @DATE and @TIME:

@DB2

Inserts the DB2 subsystem ID of the data being collected into the name of the dataset.

@DATE

Inserts the date of the first record in the dataset into the name of the dataset.

@TIME

Inserts the time of the first record in the dataset into the name of the dataset.

This field is applicable only if the storage type is VSAMSEQ, VSAMSEQTHVSAM, or SEQTHVSAM and the storage mechanism is DYNAMIC.

Required or optional

Optional (Required if KD2_PFn_HIS_START is set to C,Y and KD2_PFn_HIS_SEQ_TYP is set to D)

Default value

None

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

<value>

PARMGEN name

KD2_PFn_HIS_DYN_DSNAME

PARMGEN classification

NTH

KD2_PFn_HIS_DYN_MCLAS

Management class DYNAMIC

Description

If the historical sequential datasets are SMS-managed, then specify the SMS management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Location where the parameter value is stored

In the COPTssid member of the *rhilev.middlev.rtename*.RKD2PAR library

Output line

MGMTCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ2

Panel field

Mgmtclas

Default value

&RTESVMGT

Batch parameter name

KD2_PFn_HIS_DYN_MCLAS

PARMGEN name

KD2_PFn_HIS_DYN_MCLAS

PARMGEN classification

NTH

KD2_PF_HIS_DYN_PRIMARY

KD2_PFn_HIS_DYN_PRIMARY

Primary space for sequential datasets

Description

Specify the primary space allocation used for the sequential data sets created by the Near-Term History Data Collector. The default is 10 cylinders.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, or SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional (Required if KD2_PF_HIS_START is set to C,Y and KD2_PF_HIS_SEQ_TYP is set to D)

Default value

10

Valid values

Any number in the range 3-9999

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

SPACE(CYL,<value>,<KD2_PFn_HIS_DYN_SECONDARY>)

PARMGEN name

KD2_PFn_HIS_DYN_PRIMARY

PARMGEN classification

NTH

KD2_PFn_HIS_DYN_SCLAS

Storage class DYNAMIC

Description

If the historical sequential datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

STORCLAS(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ2

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_PF_HIS_DYN_SCLAS

PARMGEN name

KD2_PFNn_HIS_DYN_SCLAS

PARMGEN classification

NTH

KD2_PFNn_HIS_DYN_SECONDARY

Secondary space for sequential datasets

Description

Specify the secondary space allocation used for the sequential data sets created by the Near-Term History Data Collector. The default is 2 cylinders.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, or SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional (Required if KD2_PFN_HIS_START is set to C,Y and KD2_PFN_HIS_SEQ_TYP is set to D)

Default value

2

Valid values

Any number in the range 0-9999

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

SPACE(CYL,<KD2_PFNn_HIS_DYN_PRIMARY>,<value>)

PARMGEN name

KD2_PFNn_HIS_DYN_SECONDARY

PARMGEN classification

NTH

KD2_PFNn_HIS_DYN_SQL

The KD2_PFNn_HIS_DYN_SQL parameter specifies whether to collect dynamic SQL data.

Valid values

This specifies whether dynamic SQL text and access path information is collected.

Y: the collector activates IFCIDs 22, 63, 105, and 107.

F: the collector activates IFCIDs 22, 350, 105, and 107. IFCID 350 records the complete text of a parsed SQL statement, while IFCID 63 is limited to the first 5000 bytes of a SQL statement.

Required or optional

Optional (Required if KD2_PFN_HIS_START is set to Y.)

Default value

N

Valid values

Y, N, F

Locations where the parameter value is stored**Location 1**

In the DB2PROF member of the %RTE_HILEV%.%RTE_NAME%.RKD2PRF library

Output line

DB2_DSNTIAD=<value>NTIA

Location 2

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

KD2_PFn_HIS_DYN_UNIT

Output line

DYNAMICSQL(<value>Y)

PARMGEN name

KD2_PFn_HIS_DYN_SQL

PARMGEN classification

NTH

KD2_PFn_HIS_DYN_UNIT

Unit DYNAMIC

Description

Specify the unit name for the allocation of the historical sequential datasets. If the historical sequential datasets are not SMS-managed then this is a required entry. If your installation does not use the unit name, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_UNIT%

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

UNIT(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ2

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_PFn_HIS_DYN_UNIT

PARMGEN name

KD2_PFn_HIS_DYN_UNIT

PARMGEN classification

NTH

KD2_PFn_HIS_DYN_VOLUME

Volser DYNAMIC

Description

Specify the volume serial numbers for the allocation of the historical sequential datasets. If the historical sequential datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

VOLSER(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ2

Panel field

Volser

Default value

&RTEVV

Batch parameter name

KD2_PF_HIS_DYN_VOL

PARMGEN name

KD2_PFnn_HIS_DYN_VOLUME

PARMGEN classification

NTH

KD2_PFnn_HIS_GDG_DSNAME

Dataset name GDG

Description

Specify the name for the base dataset of the Generation Data Group GDG. For the GDG type, the dataset name can have a maximum of 35 characters. And the storage mechanism is GDG.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to C,Y and KD2_PF_HIS_SEQ_TYP is set to G)

Default value

None

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

(NAME ('<value>')) -

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

ENTRIES ('<value>') -

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ3

Panel field

Dataset name

Default value

None

KD2_PF_HIS_GDG_LIM

Batch parameter name

KD2_PF_HIS_GDG_DSNAME

PARMGEN name

KD2_PFnn_HIS_GDG_DSNAME

PARMGEN classification

NTH

KD2_PFnn_HIS_GDG_LIM

The KD2_PFnn_HIS_GDG_LIM parameter specifies the number of GDG generations to be used for this GDG.

Valid values

Any number in the range 1-255.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, or SEQTHVSAM and the storage mechanism is GDG.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to C,Y and KD2_PF_HIS_SEQ_TYP is set to G)

Default value

7

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

LIMIT(<value>))

Location 2

In the HCRVssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

LIMIT(<value>))

PARMGEN name

KD2_PFnn_HIS_GDG_LIM

PARMGEN classification

NTH

KD2_PFnn_HIS_GDG_MCLAS

Management class GDG

Description

If the historical sequential datasets are SMS-managed, then specify the SMS management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

MGMTCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ3

Panel field

Mgmtclas

Default value

&RTESVMGT

Batch parameter name

KD2_PF_HIS_GDG_MCLAS

PARMGEN name

KD2_PFn_HIS_GDG_MCLAS

PARMGEN classification

NTH

KD2_PFn_HIS_GDG_PRIMARY

The KD2_PFn_HIS_GDG_PRIMARY parameter specifies the primary space allocation used for the GDG.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to C,Y and KD2_PF_HIS_SEQ_TYP is set to G)

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, or SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Default value

10

Valid values

Any number in the range 3-9999

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

SPACE(CYL, <value>, <KD2_PFn_HIS_GDG_SECONDARY>)

PARMGEN name

KD2_PFn_HIS_GDG_PRIMARY

PARMGEN classification

NTH

KD2_PFn_HIS_GDG_SCLAS

Storage class GDG

Description

If the historical sequential datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

KD2_PF_HIS_GDG_SECONDARY

Output line

STORCLAS(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ3

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_PF_HIS_GDG_SCLAS

PARMGEN name

KD2_PFnn_HIS_GDG_SCLAS

PARMGEN classification

NTH

KD2_PFnn_HIS_GDG_SECONDARY

The KD2_PFnn_HIS_GDG_SECONDARY parameter specifies the secondary space allocation used for the GDG.

Default value

2 cylinders

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to C,Y and KD2_PF_HIS_SEQ_TYP is set to G)

Valid values

Any number in the range 0-9999

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

SPACE(CYL,<KD2_PFnn_HIS_GDG_PRIMARY>,<value>)

PARMGEN name

KD2_PFnn_HIS_GDG_SECONDARY

PARMGEN classification

NTH

KD2_PFnn_HIS_GDG_UNIT

Unit GDG

Description

Specify the unit name for the allocation of the historical sequential datasets. If the historical sequential datasets are not SMS-managed then this is a required entry. If your installation does not use the unit name, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_UNIT%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

UNIT(<value>)

Location 2

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

UNIT(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ3

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_Pf_HIS_GDG_UNIT

PARMGEN name

KD2_PFn_HIS_GDG_UNIT

PARMGEN classification

NTH

KD2_PFn_HIS_GDG_VOLUME

Volser GDG

Description

Specify the volume serial numbers for the allocation of the historical sequential datasets. If the historical sequential datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

VOLUME(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ3

Panel field

Volser

Default value

&RTEVV

KD2_PF_HIS_IFIREAD

Batch parameter name

KD2_PF_HIS_GDG_VOL

PARMGEN name

KD2_PFn_HIS_GDG_VOLUME

PARMGEN classification

NTH

KD2_PFn_HIS_IFIREAD

IFI trace read frequency

Description

Specifies the IFI trace record read time in "mmssth" format where "mmssth" is minutes, seconds, tenths and hundredths of seconds. This parameter controls the frequency with which the Near-Term History Data Collector reads the new IFI trace records into the collection buffer.

You can increase the frequency by decreasing the interval, however, CPU utilization will increase. The default is 010000 which is 1 minute.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

010000

Minimum

000100

Maximum

010000

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

IFIREADTIME(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P8

Panel field

IFI read frequency

Default value

010000

Minimum

000100

Maximum

010000

Batch parameter name

KD2_PF_HIS_IFIREAD

PARMGEN name

KD2_PFn_HIS_IFIREAD

PARMGEN classification

NTH

KD2_PFn_HIS_LOCK_CNTN

The KD2_PFn_HIS_LOCK_CNTN parameter specifies whether lock timeout and deadlock information is collected.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

N

Valid values

Y: Collector activates IFCIDs 172, 196, 105, and 107

N

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

LOCKCONT(<value>Y)

PARMGEN name

KD2_PFn_HIS_LOCK_CNTN

PARMGEN classification

NTH

KD2_PFn_HIS_LOCK_SUSP

The KD2_PFn_HIS_LOCK_SUSP parameter specifies whether to collect lock wait information for local resources.

Description

If Y is entered, the collector activates IFCIDs 44,45,213,214,105,107.

Required or optional

Optional (Required if KD2_PF_HIS_START is set to Y)

Default value

N

Valid values

Y, N

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

LOCKSUSP(<value>Y)

PARMGEN name

KD2_PFn_HIS_LOCK_SUSP

PARMGEN classification

NTH

KD2_PFn_HIS_LOG1

VSAM log dataset 1

Description

Specify a name for the VSAM log dataset to be created. Specify at least two datasets to allow for log switching. The Near-Term History Data Collector will automatically switch to a free log dataset when the current dataset is full. Near-Term History VSAM dataset names must be unique for each DB2 subsystem.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

KD2_PF_HIS_LOG2

Default value

%RTE_VSAM_HILEV%.%RTE_NAME%.%DB%.RKD2VS01

Locations where the parameter value is stored

Location 1

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

ENTRIES(' <value>') -

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

(NAME(<value>) -

Location 3

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

<value>

Location 4

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

DEFINE CLUSTER(NAME(<value>) -

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P7

Panel field

VSAM log data set name

Default value

None

Batch parameter name

KD2_PF_HIS_LOG1

PARMGEN name

KD2_PFn_HIS_LOG1

PARMGEN classification

NTH

KD2_PFn_HIS_LOG2

The KD2_PFn_HIS_LOG2 parameter specifies a name for the VSAM log data set to be created

Specify at least two data sets to allow for log switching. The Near-Term History Data Collector will automatically switch to a free log data set when the current data set is full. Near-Term History VSAM data set names must be unique for each DB2 subsystem.

Required or optional

Optional (Required if KD2_PF_HIS_START is set to Y)

Default value

%RTE_VSAM_HILEV%.%RTE_NAME%.%DB%.RKD2VS02

Locations where the parameter value is stored

Location 1

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

ENTRIES(' <value> ') -

Location 2

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

(NAME(<value>)) -

Location 3

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

<value>

Location 4

In the HCRVssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

DEFINE CLUSTER(NAME(<value>) -

PARMGEN name

KD2_PFn_HIS_LOG2

PARMGEN classification

NTH

KD2_PFn_HIS_LOG2

The KD2_PFn_HIS_LOG2 parameter specifies a name for the VSAM log data set to be created

Specify at least two data sets to allow for log switching. The Near-Term History Data Collector will automatically switch to a free log data set when the current data set is full. Near-Term History VSAM data set names must be unique for each DB2 subsystem.

Required or optional

Optional (Required if KD2_PF_HIS_START is set to Y)

Default value

%RTE_VSAM_HILEV%.%RTE_NAME%.%DB%.RKD2VS02

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

ENTRIES(' <value> ') -

Location 2

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

(NAME(<value>)) -

Location 3

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

<value>

Location 4

In the HCRVssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

DEFINE CLUSTER(NAME(<value>) -

PARMGEN name

KD2_PFn_HIS_LOG2

PARMGEN classification

NTH

KD2_PFn_HIS_LOG3

VSAM log dataset 3

Description

Specify a name for the VSAM log dataset to be created. Specify at least two datasets to allow for log switching. The Near-Term History Data Collector will automatically switch to a free log dataset when the current dataset is full. Near-Term History VSAM dataset names must be unique for each DB2 subsystem.

Required or optional

Optional

Default value

%RTE_VSAM_HILEV%.%RTE_NAME%.%DB%.RKD2VS03

Locations where the parameter value is stored**Location 1**In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library**Output line**

(NAME(<value>) -

Location 2In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library**Output line**

ENTRIES(' <value> ') -

Location 3In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library**Output line**

<value>

Location 4In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library**Output line**

DEFINE CLUSTER(NAME(<value>) -

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

VSAM log data set name

Default value

None

Batch parameter name

KD2_PF_HIS_LOG3

PARMGEN name

KD2_PFn_HIS_LOG3

PARMGEN classification

NTH

KD2_PFnn_HIS_LOG4

VSAM log dataset 4

Description

Specify a name for the VSAM log dataset to be created. Specify at least two datasets to allow for log switching. The Near-Term History Data Collector will automatically switch to a free log dataset when the current dataset is full. Near-Term History VSAM dataset names must be unique for each DB2 subsystem.

Required or optional

Optional

Default value

%RTE_VSAM_HILEV%.%RTE_NAME%.%DB%.RKD2VS04

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

(NAME(<value>) -

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

ENTRIES(' <value> ') -

Location 3

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

<value>

Location 4

In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

DEFINE CLUSTER(NAME(<value>) -

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

VSAM log data set name

Default value

None

Batch parameter name

KD2_PF_HIS_LOG4

PARMGEN name

KD2_PFnn_HIS_LOG4

PARMGEN classification

NTH

KD2_PFnn_HIS_LOG5

VSAM log dataset 5

Description

Specify a name for the VSAM log dataset to be created. Specify at least two datasets to allow for log switching. The Near-Term History Data Collector will automatically switch to a free log dataset when the current dataset is full. Near-Term History VSAM dataset names must be unique for each DB2 subsystem.

Required or optional

Optional

Default value

%RTE_VSAM_HILEV%.%RTE_NAME%.%DB%.RKD2VS05

Locations where the parameter value is stored**Location 1**In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

(NAME(<value>) -

Location 2In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

ENTRIES(' <value> ') -

Location 3In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

<value>

Location 4In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

DEFINE CLUSTER(NAME(<value>) -

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

VSAM log data set name

Default value

None

Batch parameter name

KD2_PF_HIS_LOG5

PARMGEN name

KD2_PFnn_HIS_LOG5

PARMGEN classification

NTH

KD2_PFnn_HIS_LOG6

VSAM log dataset 6

Description

Specify a name for the VSAM log dataset to be created. Specify at least two datasets to allow for log switching. The Near-Term History Data Collector will automatically switch to a free log dataset when the current dataset is full. Near-Term History VSAM dataset names must be unique for each DB2 subsystem.

Required or optional

Optional

Default value

%RTE_VSAM_HILEV%.%RTE_NAME%.%DB%.RKD2VS06

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

(NAME(<value>) -

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

ENTRIES(' <value> ') -

Location 3

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

<value>

Location 4

In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

DEFINE CLUSTER(NAME(<value>) -

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

VSAM log data set name

Default value

None

Batch parameter name

KD2_PF_HIS_LOG6

PARMGEN name

KD2_PFnn_HIS_LOG6

PARMGEN classification

NTH

KD2_PFnn_HIS_LOG7

VSAM log dataset 7

Description

Specify a name for the VSAM log dataset to be created. Specify at least two datasets to allow for log switching. The Near-Term History Data Collector will automatically switch to a free log dataset when the current dataset is full. Near-Term History VSAM dataset names must be unique for each DB2 subsystem.

Required or optional

Optional

Default value

%RTE_VSAM_HILEV%.%RTE_NAME%.%DB%.RKD2VS07

Locations where the parameter value is stored**Location 1**In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

(NAME(<value>) -

Location 2In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

ENTRIES(' <value> ') -

Location 3In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

<value>

Location 4In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

DEFINE CLUSTER(NAME(<value>) -

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

VSAM log data set name

Default value

None

Batch parameter name

KD2_Pf_HIS_LOG7

PARMGEN name

KD2_PFnn_HIS_LOG7

PARMGEN classification

NTH

KD2_PFn_HIS_NEQSQL

Negative SQL option

Description

Specifies whether or not the number of SQL calls executed by a thread which resulted in a negative return code is collected. If Y is entered, the collector activates IFCIDs 58,59,60,61,62,64,65 and 66 to the DB2 START TRACE PERFORMANCE command.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

NEGSQL (<value>Y)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PB

Panel field

Negative SQL

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_HIS_NEQSQL

PARMGEN name

KD2_PFn_HIS_NEQSQL

PARMGEN classification

NTH

KD2_PFn_HIS_POSTPCT

Threshold for historical collection

Description

Specifies the option to tune the Near-Term History Data Collector if you often see the DSNW133I messages issued by DB2. This value is used to compute a "high water mark" or threshold for historical collection. This threshold is a percentage of the total number of bytes in the IFI buffer. When this threshold is exceeded, DB2 will post the Near-Term History Data Collector to drain the buffer. The Near-Term History Data Collector will allow any percentage value from 1-99. Start from the default value of 70 and test small increments up or down.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

70

KD2_PF_HIS_SCAN_SUMM

Minimum

1

Maximum

99

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

POSTPCT(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

Threshold

Default value

70

Minimum

1

Maximum

99

Batch parameter name

KD2_PF_HIS_POSTPCT

PARMGEN name

KD2_PFnn_HIS_POSTPCT

PARMGEN classification

NTH

KD2_PFnn_HIS_SCAN_SUMM

The KD2_PFnn_HIS_SCAN_SUMM parameter specifies whether to collect scan summary data.

Description

If Y is entered, the collector activates IFCIDs 15,16,17,18.

Required or optional

Optional (Required if KD2_PF_HIS_START is set to Y)

Default value

N

Valid values

Y, N

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

SCAN(<value>Y)

PARMGEN name

KD2_PFnn_HIS_SCAN_SUMM

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQLOG1

The KD2_PFnn_HIS_SEQLOG1 parameter specifies names for up to 7 sequential data sets that will be created for trace data collection.

Description

A minimum of 2 data sets is required. Ensure that the set of historical sequential data sets is unique for each DB2 subsystem.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, or SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional (Required if KD2_PF_HIS_START is set to C,Y and KD2_PF_HIS_SEQ_TYP is set to S)

Default value

None

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

```
LISTCAT ENTRIES('<value>') NAME
```

Location 2

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

```
ALLOC DSNAME('<value>') -
```

PARMGEN name

KD2_PFnn_HIS_SEQLOG1

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQLOG2

Sequential dataset 2

Description

Specify the name of sequential dataset 2. See KD2_PFnn_HIS_SEQLOG1 for details.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to C,Y and KD2_PF_HIS_SEQ_TYP is set to S)

Default value

None

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
LISTCAT ENTRIES('<value>') NAME
```

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
ALLOC DSNAME('<value>') -
```

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

KD2_PF_HIS_SEQLOG3

Panel ID

KD261PZ1

Panel field

Dataset name

Default value

None

Batch parameter name

KD2_PF_HIS_SEQLOG2

PARMGEN name

KD2_PFnn_HIS_SEQLOG2

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQLOG3

Sequential dataset 3

Description

Specify the name of sequential dataset 3. See KD2_PFnn_HIS_SEQLOG1 for details.

Required or optional

Optional

Default value

None

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
LISTCAT ENTRIES('<value>') NAME
```

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
ALLOC DSNAME('<value>') -
```

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Dataset name

Default value

None

Batch parameter name

KD2_PF_HIS_SEQLOG3

PARMGEN name

KD2_PFnn_HIS_SEQLOG3

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQLOG4

Sequential dataset 4

Description

Specify the name of sequential dataset 4. See KD2_PFnn_HIS_SEQLOG1 for details.

Required or optional

Optional

Default value

None

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
LISTCAT ENTRIES('<value>') NAME
```

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
ALLOC DSNAME('<value>') -
```

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Dataset name

Default value

None

Batch parameter name

KD2_PF_HIS_SEQLOG4

PARMGEN name

KD2_PFnn_HIS_SEQLOG4

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQLOG5

Sequential dataset 5

Description

Specify the name of sequential dataset 5. See KD2_PFnn_HIS_SEQLOG1 for details.

Required or optional

Optional

Default value

None

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
LISTCAT ENTRIES('<value>') NAME
```

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

ALLOC DSNAME('<value>') -

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Dataset name

Default value

None

Batch parameter name

KD2_PF_HIS_SEQLOG5

PARMGEN name

KD2_PFnn_HIS_SEQLOG5

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQLOG6

Sequential dataset 6

Description

Specify the name of sequential dataset 6. See KD2_PFnn_HIS_SEQLOG1 for details.

Required or optional

Optional

Default value

None

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

LISTCAT ENTRIES('<value>') NAME

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

ALLOC DSNAME('<value>') -

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Dataset name

Default value

None

Batch parameter name

KD2_PF_HIS_SEQLOG6

PARMGEN name

KD2_PFNn_HIS_SEQLOG6

PARMGEN classification

NTH

KD2_PFNn_HIS_SEQLOG7

Sequential dataset 7

Description

Specify the name of sequential dataset 7. See KD2_PFNn_HIS_SEQLOG1 for details.

Required or optional

Optional

Default value

None

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
LISTCAT ENTRIES('<value>') NAME
```

Location 2

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
ALLOC DSNAME('<value>') -
```

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Dataset name

Default value

None

Batch parameter name

KD2_PFN_HIS_SEQLOG7

PARMGEN name

KD2_PFNn_HIS_SEQLOG7

PARMGEN classification

NTH

KD2_PFNn_HIS_SEQ_ARC_DS

The KD2_PFNn_HIS_SEQ_ARC_DS parameter specifies the name of the archive data set.

Description

If you selected GDG, specify the following parameters:

Specify the name for the base data set of the Generation Data Group GDG. For the GDG type, the data set name can have a maximum of 35 characters.

If you selected DYN, specify the following parameters:

Use the following variables to construct the sequential data set name. To ensure unique data set names, you must use at least @DB2, @DATE and @TIME:

KD2_PF_HIS_SEQ_ARC_GDGLIM

@DB2

Inserts the DB2 subsystem ID of the data being collected into the name of the data set.

@DATE

Inserts the date of the first record in the data set into the name of the data set.

@TIME

Inserts the time of the first record in the data set into the name of the data set.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to C,Y and KD2_PF_HIS_SEQ_TYP is set to S)

Default value

None

Locations where the parameter value is stored

Location 1

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

(NAME ('<value>')) -

Location 2

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

ENTRIES ('<value>') -

PARMGEN name

KD2_PFnn_HIS_SEQ_ARC_DS

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQ_ARC_GDGLIM

GDG Limit for the archive dataset

Description

Specify the number of GDG generations to be used for this GDG. You can specify 1 to 255.

This field is only applicable if you specified GDG as the storage mechanism to be used for archiving.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to C,Y and KD2_PF_HIS_SEQ_TYP is set to S and KD2_PF_HIS_SEQ_ARC_TYP is set to GDG)

Default value

7

Minimum

1

Maximum

255

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

LIMIT(<value>))

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZA

Panel field

Limit for GDG data sets

Default value

7

Minimum

1

Maximum

255

Batch parameter name

KD2_PF_HIS_SEQ_ARC_GDGLIM

PARMGEN name

KD2_PFn_HIS_SEQ_ARC_GDGLIM

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_ARC_MCLAS

The KD2_PFn_HIS_SEQ_ARC_MCLAS parameter specifies the management class for archive data sets.

Description

If the data set is SMS-managed, specify the SMS management class to use on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, or SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_MGMTCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

MGMTCLAS(<value>)

Location 2

In the HCRVssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

MGMTCLAS(<value>)

PARMGEN name

KD2_PFn_HIS_SEQ_ARC_MCLAS

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_ARC_SCLAS

Storage class for the archive datasets

Description

If the dataset is SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

KD2_PF_HIS_SEQ_ARC_TYP

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_STORCLAS%

Locations where the parameter value is stored

Location 1

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

STORCLAS(<value>)

Location 2

In the HCRVssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

STORCLAS(<value>)

PARMGEN name

KD2_PFn_HIS_SEQ_ARC_SCLAS

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_ARC_TYP

The KD2_PFn_HIS_SEQ_ARC_TYP parameter specifies the storage mechanism for archive data sets.

Description

You configured the Near-Term History Data Collector to store the trace data to VSAM data sets and sequential data sets VSAMSEQ, VSAMSEQTHVSAM, or SEQTHVSAM and you specified the storage mechanism.

On this panel you can specify the information used to create the archive data sets that are generated by the Near-Term History Data Collector. There are two choices:

GDG

Generation Data Group

DYN

the Near-Term History Data Collector always allocates a new data set when the currently used data set is full.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to C,Y and KD2_PF_HIS_SEQ_TYP is set to S)

Default value

GDG

Permissible values

GDG, DYN

Location where the parameter value is stored

This value is not stored in a configuration member.

PARMGEN name

KD2_PFn_HIS_SEQ_ARC_TYP

PARMGEN classification

NTH

KD2_PFN_HIS_SEQ_ARC_UNIT

The KD2_PFN_HIS_SEQ_ARC_UNIT parameter specifies the unit for the archive data sets.

Description

Specify the unit name for the allocation of the data set. If the data set is not SMS-managed, this parameter is required. If your installation does not use unit name, leave this field blank.

Required or optional

Optional

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Default value

%RTE_SMS_UNIT%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

UNIT(<value>)

Location 2

In the HCRVssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

UNIT(<value>)

PARMGEN name

KD2_PFN_HIS_SEQ_ARC_UNIT

PARMGEN classification

NTH

KD2_PFN_HIS_SEQ_ARC_VOLUME

The KD2_PFN_HIS_SEQ_ARC_VOLUME parameter specifies the volume serial (volser) range for the archive data sets.

Description

If the data set is not to be SMS-managed, this is required. If your installation does not use volume serial number, leave this field blank.

Required or optional

Optional

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, or SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Default value

%RTE_SMS_VOLUME%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

VOLUME(<value>)

Location 2

In the HCRVssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

VOLUME(<value>)

KD2_PF_HIS_SEQ_MCLAS1

PARMGEN name

KD2_PFnn_HIS_SEQ_ARC_VOLUME

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQ_MCLAS1

The KD2_PFnn_HIS_SEQ_MCLAS1 parameter specifies the SMS management class for sequential data set 1.

Description

If the historical sequential data sets are SMS-managed, then specify the SMS management class to use on the allocation. If your installation does not use the SMS MGMTCLAS parameter, leave this field blank.

Required or optional

Optional

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Default value

%RTE_SMS_MGMTCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

MGMTCLAS(<value>) +

PARMGEN name

KD2_PFnn_HIS_SEQ_MCLAS1

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQ_MCLAS2

The KD2_PFnn_HIS_SEQ_MCLAS2 parameter specifies the SMS management class for sequential data set 2.

Description

If the historical sequential data sets are SMS-managed, then specify the SMS management class to use on the allocation. If your installation does not use the SMS MGMTCLAS parameter, leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, or SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_MGMTCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

MGMTCLAS(<value>) +

PARMGEN name

KD2_PFnn_HIS_SEQ_MCLAS2

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_MCLAS3

The KD2_PFn_HIS_SEQ_MCLAS3 parameter specifies the SMS management class for sequential data set 3.

Description

If the historical sequential data sets are SMS-managed, then specify the SMS management class to use on the allocation. If your installation does not use the SMS MGMTCLAS parameter, leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_MGMTCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

MGMTCLAS(<value>) +

PARMGEN name

KD2_PFn_HIS_SEQ_MCLAS3

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_MCLAS4

The KD2_PFn_HIS_SEQ_MCLAS4 parameter specifies the management class for sequential data set 4

Description

If the historical sequential data sets are SMS-managed, specify the SMS management class to use on the allocation. If your installation does not use the SMS MGMTCLAS parameter, leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_MGMTCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

MGMTCLAS(<value>) +

PARMGEN name

KD2_PFn_HIS_SEQ_MCLAS4

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_MCLAS5

The KD2_PFn_HIS_SEQ_MCLAS5 parameter specifies the management class for sequential data set 5.

Description

If the historical sequential data sets are SMS-managed, specify the SMS management class to use on the allocation. If your installation does not use the SMS MGMTCLAS parameter, leave this field blank.

KD2_PF_HIS_SEQ_MCLAS6

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_MGMTCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

MGMTCLAS(<value>) +

PARMGEN name

KD2_PFn_HIS_SEQ_MCLAS5

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_MCLAS6

The KD2_PFn_HIS_SEQ_MCLAS6 parameter specifies the management class for sequential data set 6.

Description

If the historical sequential data sets are SMS-managed, specify the SMS management class to use on the allocation. If your installation does not use the SMS MGMTCLAS parameter, leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_MGMTCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

MGMTCLAS(<value>) +

PARMGEN name

KD2_PFn_HIS_SEQ_MCLAS6

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_MCLAS7

Mgmt Class for sequential dataset 7

Description

If the historical sequential datasets are SMS-managed, then specify the SMS management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_MGMTCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

MGMTCLAS(<value>) +

PARMGEN name

KD2_PFN_HIS_SEQ_MCLAS7

PARMGEN classification

NTH

KD2_PFN_HIS_SEQ_PRIMARY_CYL

Primary space for sequential datasets

Description

Specify the primary space allocation used for the sequential datasets. The default is 10 cylinders.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional (Required in case KD2_PFN_HIS_START is set to C,Y and KD2_PFN_HIS_SEQ_TYP is set to S)

Default value

10

Minimum

3

Maximum

9999

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

DSORG(PS) SPACE(<value> <KD2_PFN_HIS_SEQ_SECONDARY_CYL>) CYLINDERS

Location 2

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

SPACE(CYL, <value>, <KD2_PFN_HIS_SEQ_SECONDARY_CYL>)

PARMGEN name

KD2_PFN_HIS_SEQ_PRIMARY_CYL

PARMGEN classification

NTH

KD2_PFN_HIS_SEQ_SCLAS1

Storage class for sequential dataset 1

Description

If the historical sequential datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

KD2_PFn_HIS_SEQ_SCLAS2

Default value

%RTE_SMS_STORCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

STORCLAS(<value>) +

PARMGEN name

KD2_PFn_HIS_SEQ_SCLAS1

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_SCLAS2

Storage class for sequential dataset 2

Description

If the historical sequential datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_STORCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

STORCLAS(<value>) +

PARMGEN name

KD2_PFn_HIS_SEQ_SCLAS2

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_SCLAS3

Storage class for sequential dataset 3

Description

If the historical sequential datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_STORCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

STORCLAS(<value>) +

PARMGEN name

KD2_PFn_HIS_SEQ_SCLAS3

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_SCLAS4

Storage class for sequential dataset 4

Description

If the historical sequential datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_STORCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

STORCLAS(<value>) +

PARMGEN name

KD2_PFn_HIS_SEQ_SCLAS4

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_SCLAS5

Storage class for sequential dataset 5

Description

If the historical sequential datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_STORCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

STORCLAS(<value>) +

PARMGEN name

KD2_PFn_HIS_SEQ_SCLAS5

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_SCLAS6

KD2_PFn_HIS_SEQ_SCLAS6

Storage class for sequential dataset 6

Description

If the historical sequential datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_STORCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

STORCLAS(<value>) +

PARMGEN name

KD2_PFn_HIS_SEQ_SCLAS6

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_SCLAS7

The KD2_PFn_HIS_SEQ_SCLAS7 parameter specifies the storage class for sequential dataset 7

Description

If the historical sequential datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_STORCLAS%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

STORCLAS(<value>) +

PARMGEN name

KD2_PFn_HIS_SEQ_SCLAS7

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_SECONDARY_CYL

Secondary space for sequential datasets

Description

Specify the secondary space allocation used for the sequential datasets. The default is 2 cylinders.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional (Required in case KD2_PFn_HIS_START is set to C,Y and KD2_PFn_HIS_SEQ_TYP is set to S)

Default value

2

Minimum

0

Maximum

9999

Locations where the parameter value is stored

Location 1

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

DSORG(PS) SPACE(<KD2_PFn_HIS_SEQ_PRIMARY_CYL> <value>) CYLINDERS

Location 2

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

SPACE(CYL,<KD2_PFn_HIS_SEQ_PRIMARY_CYL>,<value>)

PARMGEN name

KD2_PFn_HIS_SEQ_SECONDARY_CYL

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_TYP

Storage mechanism

Description

If you specified VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM you can choose one of the following 3 alternatives to store trace data in sequential files:

Static sequential S

You may specify 2 to 7 sequential datasets for trace data collection. When the first dataset is full the Near-Term History Data Collector switches to the next available dataset. When the last available dataset in the sequence is full, the Near-Term History Data Collector switches to the first dataset in the sequence again and overwrites the data in the first dataset. Each time the Near-Term History Data Collector switches to a full sequential dataset to overwrite it, you can archive its content to additional sequential datasets.

Dynamic sequential D

The Near-Term History Data Collector always allocates a new dataset when the currently used dataset becomes full. As a result, the collected data is not overwritten.

GDG G

In this case a Generation Data Group GDG is used. The mechanism is similar to the one described for the storage type Static sequential. When all datasets are full the Near-Term History Data Collector overwrites the trace data in the first dataset. However, in a GDG, the z/OS, not the Near-Term History Data Collector, switches between the different datasets generations. For this alternative archiving is not supported.

Required or optional

Optional (Required in case KD2_PFn_HIS_START is set to C,Y and KD2_PFn_HIS_STORE is set to VSAMSEQ,VSAMSEQTHVSAM,SEQTHVSAM)

Default value

S

KD2_PF_HIS_SEQ_UNIT1

Permissible values

S, D, G

Location where the parameter value is stored

This value is not stored in a configuration member.

PARMGEN name

KD2_PFn_HIS_SEQ_TYP

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_UNIT1

Unit for sequential dataset 1

Description

Specify the unit name for the allocation of the historical sequential datasets. If the historical sequential datasets are not SMS-managed then this is a required entry. If your installation does not use the unit name, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_UNIT%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

UNIT(<value>) +

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ1

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_PF_HIS_SEQ_UNIT1

PARMGEN name

KD2_PFn_HIS_SEQ_UNIT1

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_UNIT2

Unit for sequential dataset 2

Description

Specify the unit name for the allocation of the historical sequential datasets. See KD2_PFn_HIS_SEQ_UNIT1 for details.

Required or optional

Optional

Default value

%RTE_SMS_UNIT%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

UNIT(<value>) +

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_PF_HIS_SEQ_UNIT2

PARMGEN name

KD2_PFnn_HIS_SEQ_UNIT2

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQ_UNIT3

Unit for sequential dataset 3

Description

Specify the unit name for the allocation of the historical sequential datasets. See KD2_PFnn_HIS_SEQ_UNIT1 for details.

Required or optional

Optional

Default value

%RTE_SMS_UNIT%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

UNIT(<value>) +

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_PF_HIS_SEQ_UNIT3

PARMGEN name

KD2_PFnn_HIS_SEQ_UNIT3

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_UNIT4

KD2_PFn_HIS_SEQ_UNIT4

Unit for sequential dataset 4

Description

Specify the unit name for the allocation of the historical sequential datasets. See KD2_PFn_HIS_SEQ_UNIT1 for details.

Required or optional

Optional

Default value

%RTE_SMS_UNIT%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

UNIT(<value>) +

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ1

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_PFn_HIS_SEQ_UNIT4

PARMGEN name

KD2_PFn_HIS_SEQ_UNIT4

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_UNIT5

Unit for sequential dataset 5

Description

Specify the unit name for the allocation of the historical sequential datasets. See KD2_PFn_HIS_SEQ_UNIT1 for details.

Required or optional

Optional

Default value

%RTE_SMS_UNIT%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

UNIT(<value>) +

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ1

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_PF_HIS_SEQ_UNIT5

PARMGEN name

KD2_PFnn_HIS_SEQ_UNIT5

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQ_UNIT6

Unit for sequential dataset 6

Description

Specify the unit name for the allocation of the historical sequential datasets. See KD2_PFnn_HIS_SEQ_UNIT1 for details.

Required or optional

Optional

Default value

%RTE_SMS_UNIT%

Location where the parameter value is storedIn the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

UNIT(<value>) +

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_PF_HIS_SEQ_UNIT6

PARMGEN name

KD2_PFnn_HIS_SEQ_UNIT6

PARMGEN classification

NTH

KD2_PFnn_HIS_SEQ_UNIT7

Unit for sequential dataset 7

Description

Specify the unit name for the allocation of the historical sequential datasets. See KD2_PFnn_HIS_SEQ_UNIT1 for details.

Required or optional

Optional

KD2_PF_HIS_SEQ_VOLUME1

Default value

%RTE_SMS_UNIT%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

UNIT(<value>) +

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ1

Panel field

Unit

Default value

&RTEU

Batch parameter name

KD2_PF_HIS_SEQ_UNIT7

PARMGEN name

KD2_PFn_HIS_SEQ_UNIT7

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_VOLUME1

Volser for sequential dataset 1

Description

Specify the volume serial number for the allocation of the historical sequential dataset. If the historical sequential datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

This field is only applicable if the storage type is VSAMSEQ, VSAMSEQTHVSAM, SEQTHVSAM and the storage mechanism is STATIC SEQUENTIAL.

Required or optional

Optional

Default value

%RTE_SMS_VOLUME%

Location where the parameter value is stored

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

VOLUME(<value>) +

PARMGEN name

KD2_PFn_HIS_SEQ_VOLUME1

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_VOLUME2

Volser for sequential dataset 2

Description

Specify the volume serial number for the allocation of the historical sequential dataset. See KD2PF_HIS_SEQ_VOL1 for details.

Required or optional

Optional

Default value

%RTE_SMS_VOLUME%

Location where the parameter value is storedIn the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library**Output line**

VOLUME(<value>) +

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Volser

Default value

&RTEV

Batch parameter name

KD2_PF_HIS_SEQ_VOL2

PARMGEN name

KD2_PFn_HIS_SEQ_VOLUME2

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_VOLUME3

Volser for sequential dataset 3

Description

Specify the volume serial number for the allocation of the historical sequential dataset. See KD2PF_HIS_SEQ_VOL1 for details.

Required or optional

Optional

Default value

%RTE_SMS_VOLUME%

Location where the parameter value is storedIn the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library**Output line**

VOLUME(<value>) +

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Volser

Default value

&RTEV

Batch parameter name

KD2_PF_HIS_SEQ_VOL3

KD2_PFn_HIS_SEQ_VOLUME4

PARMGEN name

KD2_PFn_HIS_SEQ_VOLUME3

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_VOLUME4

Volser for sequential dataset 4

Description

Specify the volume serial number for the allocation of the historical sequential dataset. See KD2PF_HIS_SEQ_VOL1 for details.

Required or optional

Optional

Default value

%RTE_SMS_VOLUME%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>) +

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Volser

Default value

&RTEV

Batch parameter name

KD2_PFn_HIS_SEQ_VOL4

PARMGEN name

KD2_PFn_HIS_SEQ_VOLUME4

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_VOLUME5

Volser for sequential dataset 5

Description

Specify the volume serial number for the allocation of the historical sequential dataset. See KD2PF_HIS_SEQ_VOL1 for details.

Required or optional

Optional

Default value

%RTE_SMS_VOLUME%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>) +

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Volser

Default value

&RTEV

Batch parameter name

KD2_PF_HIS_SEQ_VOL5

PARMGEN name

KD2_PFn_HIS_SEQ_VOLUME5

PARMGEN classification

NTH

KD2_PFn_HIS_SEQ_VOLUME6

Volser for sequential dataset 6

Description

Specify the volume serial number for the allocation of the historical sequential dataset. See KD2PF_HIS_SEQ_VOL1 for details.

Required or optional

Optional

Default value

%RTE_SMS_VOLUME%

Location where the parameter value is storedIn the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

VOLUME(<value>) +

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PZ1

Panel field

Volser

Default value

&RTEV

Batch parameter name

KD2_PF_HIS_SEQ_VOL6

PARMGEN name

KD2_PFn_HIS_SEQ_VOLUME6

PARMGEN classification

NTH

KD2_PF_HIS_SEQ_VOLUME7

KD2_PFn_HIS_SEQ_VOLUME7

Volser for sequential dataset 7

Description

Specify the volume serial number for the allocation of the historical sequential dataset. See KD2PF_HIS_SEQ_VOL1 for details.

Required or optional

Optional

Default value

%RTE_SMS_VOLUME%

Location where the parameter value is stored

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>) +

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261PZ1

Panel field

Volser

Default value

&RTEV

Batch parameter name

KD2_PF_HIS_SEQ_VOL7

PARMGEN name

KD2_PFn_HIS_SEQ_VOLUME7

PARMGEN classification

NTH

KD2_PFn_HIS_SORT_SUMM

Collect sort summary data

Description

This specifies whether sort data is collected.

If Y is entered, the collector activates IFCIDs 95 and 96.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

SORT(<value>Y)

PARMGEN name

KD2_PFn_HIS_SORT_SUMM

PARMGEN classification

NTH

KD2_PFN_HIS_START

Start Near-Term History

Description

Controls whether Near-Term History is to be configured and automatically started at Server startup.

Y

Configure and autostart Near-Term History.

C

Configure, but do not autostart Near-Term History. All required configuration members are generated and datasets are allocated. Near-Term History can be started via operator commands later. See Configuration and Customization Guide.

N

Near-Term History is not configured and as result cannot be started via operator command.

Required or optional

Required

Default value

N

Permissible values

Y, N, C

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261PX

Panel field

Start Near-Term History

Default value

N

Permissible values

Y, N, C

Batch parameter name

KD2_PFN_HIS_START

PARMGEN name

KD2_PFN_HIS_START

PARMGEN classification

NTH

KD2_PFN_HIS_STORE

Storage type

Description

The data collected by Near-Term History is stored in VSAM datasets. If you want to make the data available for long-term history analysis with the Batch Reporter component, it has to be stored in sequential files in addition to VSAM datasets. If you want to collect Thread history data for Enhanced 3270UI, THVSAM should be specified. Specify one of the following values for storage type:

VSAM

Store the data to VSAM datasets for OMEGAMON DB2 Classic near-term-history (NTH) support.

VSAMSEQ

Store the data to VSAM datasets and sequential files for OMEGAMON DB2 Classic NTH support.

THVSAM

Store the data to VSAM datasets for Enhanced 3270UI Thread history support.

VSAMSEQTHVSAM

Store the data to VSAM datasets, sequential files for OMEGAMON DB2 Classic NTH support and VSAM datasets for Enhanced 3270UI Thread history support.

SEQTHVSAM

Store the data to sequential files for OMEGAMON DB2 Classic NTH support and VSAM datasets for Enhanced 3270UI Thread history support.

VSAMTHVSAM

Store the data to VSAM datasets for OMEGAMON DB2 Classic NTH support and VSAM datasets for Enhanced 3270UI Thread history support.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

VSAM

Permissible values

VSAM, VSAMSEQ, THVSAM, VSAMSEQTHVSAM, SEQTHVSAM, VSAMTHVSAM

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

WRITEOPTION(<value>)

PARMGEN name

KD2_PFnn_HIS_STORE

PARMGEN classification

NTH

KD2_PFnn_HIS_SUBINT

Collection sub-interval

Description

Specifies the number of minutes or seconds to be used as the smallest time grouping for display of historical thread accounting data. The sub-interval should be specified as a period of time for convenient display of the threads executed. The more threads are executed per minute the smaller the sub-interval that you may want to specify.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

5

Minimum

1

Maximum

60

Locations where the parameter value is stored**Location 1**

In the COPTssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

NTAINTERVAL(<value>.S)

Location 2In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

NTAINTERVAL(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

Collection sub-interval

Default value

5

Minimum

1

Maximum

60

Batch parameter name

KD2_PF_HIS_SUBINT

PARMGEN name

KD2_PFnn_HIS_SUBINT

PARMGEN classification

NTH

KD2_PFnn_HIS_SUBINT_UNIT

Collection sub-interval time unit

Description

Specifies the collection sub-interval time unit to be used to display the historical thread accounting data. Specify M for minutes or S for seconds.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

M

Permissible values

M, S

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

Collection sub-interval unit

Default value

M

KD2_PF_HIS_SEQ_VOLUME7

Permissible values

M, S

Batch parameter name

KD2_PF_HIS_SUBINT_UNIT

PARMGEN name

KD2_PFnn_HIS_SUBINT_UNIT

PARMGEN classification

NTH

KD2_PFnn_HIS_SUSPCOLL

Suspend data collection

Description

Specifies the option that controls memory usage by the Near-Term History Data Collector during times when no VSAM dataset is available. A VSAM file is considered unavailable from the time all allocated file space is used until the end of a successful flush job execution. The 'Y' option causes the collector to discard the collected trace data until a VSAM file becomes available for use. The 'N' option causes the Near-Term History Data Collector to accumulate trace data to memory until a VSAM file becomes available for use.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

Y

Permissible values

Y, N

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SUSPCOLL(<value>Y)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P8

Panel field

Suspend data collection

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_PF_HIS_SUSPCOLL

PARMGEN name

KD2_PFnn_HIS_SUSPCOLL

PARMGEN classification

NTH

KD2_PFN_HIS_VSAM_MB

Primary space for the VSAM log data sets.

Description

Specify the primary space allocation used for the VSAM log data sets. Please refer to the Configuration and Customization Guide for information about VSAM data set space requirements.

This parameter depends on the unit for the primary log space set in KD2_PFN_HIS_VSAM_SU.

CYLS

Specify the primary space for the VSAM log data sets in cylinders. The minimum is 3 and the maximum is 9999 cylinders.

Note: Depending on the disk device type, the maximum number of cylinders might need to be lower than 9999 to avoid exceeding the 2048 megabyte limit. For example, on a 3390 device, the limit of 2048 megabytes is reached with about 2600 cylinders.

MB

Specify the primary space for the VSAM log data sets in megabytes. The minimum is 1 and the maximum is 2048 megabytes.

Required or optional

Optional (Required in case KD2_PFN_HIS_START is set to Y)

Default value

900

Minimum

1

Maximum

9999

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library.

Note: Also used in the standalone version of the thread history allocation jobs (TCRV&dbid thread history to allocate the %KD2_OMPE_VSAM_DSHLQ%.%DB%.RKTH* VSAMs for thread history), and HCRV&dbid Classic near-term history VSAMs %KD2_PFN_HIS_LOGn%, which is the RKD2VSnn VSAMs for near-term history in the Classic interface).

Output line

CYLINDERS(<value> 0) -

Location 2

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

MEGABYTES(<value> 0) -

Location 3

In the HCRVssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

<KD2_PFN_HIS_VSAM_SU>(<value> 0) -

PARMGEN name

KD2_PFN_HIS_VSAM_MB

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_MCLAS1

Management class for VSAM dataset 1

Description

If the VSAM datasets are SMS-managed, then specify the SMS Management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

MGMTCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

MGMTCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Mgmtclas

Default value

&RTESVMGT

Batch parameter name

KD2_PF_HIS_VSAM_MCLAS1

PARMGEN name

KD2_PFn_HIS_VSAM_MCLAS1

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_MCLAS2

Management class for VSAM dataset 2

Description

If the VSAM datasets are SMS-managed, then specify the SMS Management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

MGMTCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

MGMTCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Mgmtclas

Default value

&RTESVMGT

Batch parameter name

KD2_PF_HIS_VSAM_MCLAS2

PARMGEN name

KD2_PFn_HIS_VSAM_MCLAS2

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_MCLAS3

Management class for VSAM dataset 3

Description

If the VSAM datasets are SMS-managed, then specify the SMS Management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

MGMTCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

MGMTCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Mgmtclas

Default value

&RTESVMGT

Batch parameter name

KD2_PF_HIS_VSAM_MCLAS3

PARMGEN name

KD2_PFnn_HIS_VSAM_MCLAS3

PARMGEN classification

NTH

KD2_PFnn_HIS_VSAM_MCLAS4

Management class for VSAM dataset 4

Description

If the VSAM datasets are SMS-managed, then specify the SMS Management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Locations where the parameter value is stored**Location 1**In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

MGMTCLAS(<value>)

Location 2In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

MGMTCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Mgmtclas

Default value

&RTESVMGT

Batch parameter name

KD2_PF_HIS_VSAM_MCLAS4

PARMGEN name

KD2_PFnn_HIS_VSAM_MCLAS4

PARMGEN classification

NTH

KD2_PFN_HIS_VSAM_MCLAS5

Management class for VSAM dataset 5

Description

If the VSAM datasets are SMS-managed, then specify the SMS Management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

MGMTCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

MGMTCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Mgmtclas

Default value

&RTESVMGT

Batch parameter name

KD2_PFN_HIS_VSAM_MCLAS5

PARMGEN name

KD2_PFN_HIS_VSAM_MCLAS5

PARMGEN classification

NTH

KD2_PFN_HIS_VSAM_MCLAS6

Management class for VSAM dataset 6

Description

If the VSAM datasets are SMS-managed, then specify the SMS Management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

MGMTCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

MGMTCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Mgmtclas

Default value

&RTESVMGT

Batch parameter name

KD2_PF_HIS_VSAM_MCLAS6

PARMGEN name

KD2_PFn_HIS_VSAM_MCLAS6

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_MCLAS7

Management class for VSAM dataset 7

Description

If the VSAM datasets are SMS-managed, then specify the SMS Management class to be used on the allocation. If your installation does not use the SMS MGMTCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_MGMTCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

MGMTCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

MGMTCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Mgmtclas

Default value

&RTESVMGT

Batch parameter name

KD2_PF_HIS_VSAM_MCLAS7

PARMGEN name

KD2_PFn_HIS_VSAM_MCLAS7

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_SCLAS1

Storage class for VSAM dataset 1

Description

If the VSAM datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Locations where the parameter value is stored**Location 1**In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

STORCLAS(<value>)

Location 2In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library**Output line**

STORCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_PF_HIS_VSAM_SCLAS1

PARMGEN name

KD2_PFn_HIS_VSAM_SCLAS1

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_SCLAS2

Storage class for VSAM dataset 2

Description

If the VSAM datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

STORCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

STORCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_PF_HIS_VSAM_SCLAS2

PARMGEN name

KD2_PFn_HIS_VSAM_SCLAS2

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_SCLAS3

Storage class for VSAM dataset 3

Description

If the VSAM datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can or if it is optional, you may leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

STORCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

STORCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_PF_HIS_VSAM_SCLAS3

PARMGEN name

KD2_PFn_HIS_VSAM_SCLAS3

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_SCLAS4

Storage class for VSAM dataset 4

Description

If the VSAM datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can or if it is optional, you may leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

STORCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

STORCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

KD2_PF_HIS_SEQ_VOLUME7

Panel ID

KD261P7

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_PF_HIS_VSAM_SCLAS4

PARMGEN name

KD2_PFnn_HIS_VSAM_SCLAS4

PARMGEN classification

NTH

KD2_PFnn_HIS_VSAM_SCLAS5

Storage class for VSAM dataset 5

Description

If the VSAM datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can or if it is optional, you may leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

STORCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

STORCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_PF_HIS_VSAM_SCLAS5

PARMGEN name

KD2_PFnn_HIS_VSAM_SCLAS5

PARMGEN classification

NTH

KD2_PFnn_HIS_VSAM_SCLAS6

Storage class for VSAM dataset 6

Description

If the VSAM datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can or if it is optional, you may leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

STORCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

STORCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_PF_HIS_VSAM_SCLAS6

PARMGEN name

KD2_PFnn_HIS_VSAM_SCLAS6

PARMGEN classification

NTH

KD2_PFnn_HIS_VSAM_SCLAS7

Storage class for VSAM dataset 7

Description

If the VSAM datasets are SMS-managed, then specify the SMS storage class to be used on the allocation. If your installation does not use the SMS STORCLAS parameter, you can or if it is optional, you may leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_STORCLAS%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

STORCLAS(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

STORCLAS(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Storclas

Default value

&RTEVSTOR

Batch parameter name

KD2_PF_HIS_VSAM_SCLAS7

PARMGEN name

KD2_PFn_HIS_VSAM_SCLAS7

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_SU

Space units used for VSAM log datasets

Description

Specify the space units used for the VSAM log datasets allocation. The allowable values are MB - megabytes and CYLS - cylinders.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

MB

Permissible values

MB, CYLS

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

CYLINDERS(<value> 0) -

Location 2

In the ALLOCDS member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

MEGABYTES(<value> 0) -

Location 3

In the HCRVssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2SAM library

Output line

<value>(<KD2_PFN_HIS_VSAM_MB> 0) -

PARMGEN name

KD2_PFN_HIS_VSAM_SU

PARMGEN classification

NTH

KD2_PFN_HIS_VSAM_VOLUME1

Volser for VSAM dataset 1

Description

Specify the volume serial numbers for the allocation of the VSAM datasets. If VSAM datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

VOLUME(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

VOLUME(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Volser

Default value

&RTEVV

Batch parameter name

KD2_PFN_HIS_VSAM_VOL1

PARMGEN name

KD2_PFN_HIS_VSAM_VOLUME1

PARMGEN classification

NTH

KD2_PFN_HIS_VSAM_VOLUME2

Volser for VSAM dataset 2

Description

Specify the volume serial numbers for the allocation of the VSAM datasets. If VSAM datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

KD2_PF_HIS_SEQ_VOLUME7

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Locations where the parameter value is stored

Location 1

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P7

Panel field

Volser

Default value

&RTEVV

Batch parameter name

KD2_PF_HIS_VSAM_VOL2

PARMGEN name

KD2_PFnn_HIS_VSAM_VOLUME2

PARMGEN classification

NTH

KD2_PFnn_HIS_VSAM_VOLUME3

Volser for VSAM dataset 3

Description

Specify the volume serial numbers for the allocation of the VSAM datasets. If VSAM datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Locations where the parameter value is stored

Location 1

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Volser

Default value

&RTEVV

Batch parameter name

KD2_PF_HIS_VSAM_VOL3

PARMGEN name

KD2_PFn_HIS_VSAM_VOLUME3

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_VOLUME4

Volser for VSAM dataset 4

Description

Specify the volume serial numbers for the allocation of the VSAM datasets. If VSAM datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Locations where the parameter value is stored**Location 1**In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library**Output line**

VOLUME(<value>)

Location 2In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library**Output line**

VOLUME(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Volser

Default value

&RTEVV

Batch parameter name

KD2_PF_HIS_VSAM_VOL4

PARMGEN name

KD2_PFn_HIS_VSAM_VOLUME4

KD2_PF_HIS_SEQ_VOLUME7

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_VOLUME5

Volser for VSAM dataset 5

Description

Specify the volume serial numbers for the allocation of the VSAM datasets. If VSAM datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Locations where the parameter value is stored

Location 1

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P7

Panel field

Volser

Default value

&RTEVV

Batch parameter name

KD2_PF_HIS_VSAM_VOL5

PARMGEN name

KD2_PFn_HIS_VSAM_VOLUME5

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_VOLUME6

Volser for VSAM dataset 6

Description

Specify the volume serial numbers for the allocation of the VSAM datasets. If VSAM datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P7

Panel field

Volser

Default value

&RTEVV

Batch parameter name

KD2_PF_HIS_VSAM_VOL6

PARMGEN name

KD2_PFn_HIS_VSAM_VOLUME6

PARMGEN classification

NTH

KD2_PFn_HIS_VSAM_VOLUME7

Volser for VSAM dataset 7

Description

Specify the volume serial numbers for the allocation of the VSAM datasets. If VSAM datasets are not to be SMS-managed, then this is a required entry. If your installation does not use the volume serial number, you can leave this field blank.

Required or optional

Optional

Default value

%RTE_SMS_VSAM_VOLUME%

Locations where the parameter value is stored**Location 1**

In the ALLOCDS member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>)

Location 2

In the HCRVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

VOLUME(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

KD2_PF_HIS_SEQ_VOLUME7

Panel ID

KD261P7

Panel field

Volser

Default value

&RTEVV

Batch parameter name

KD2_PF_HIS_VSAM_VOL7

PARMGEN name

KD2_PFnn_HIS_VSAM_VOLUME7

PARMGEN classification

NTH

KD2_PFnn_HIS_WHEN_AUTHID

Selection criteria AUTHID

Description

Specifies selection criteria based on AUTHID. For example, if AUTH1 and AUTH2 were specified for AUTHID, only data for threads with the specified authorization identifiers would be collected.

To specify selection criteria, you can use the wildcard character *, which is for one or more characters, the suffix only, and the ?, which is for a single character.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

None

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

AUTH(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

AUTHID

Default value

None

Batch parameter name

KD2_PF_HIS_WHEN_AUTHID

PARMGEN name

KD2_PFnn_HIS_WHEN_AUTHID

PARMGEN classification

NTH

KD2_PFn_HIS_WHEN_CONNID

Selection criteria CONNID

Description

Specifies selection criteria based on CONNID. For example, if CON01 and CON02 were specified for CONNID, only data for threads that use the specified connections would be collected.

To specify selection criteria, you can use the wildcard character *, which is for one or more characters, the suffix only, and the ?, which is for a single character.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

None

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

CONN(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

CONNID

Default value

None

Batch parameter name

KD2_PF_HIS_WHEN_CONNID

PARMGEN name

KD2_PFn_HIS_WHEN_CONNID

PARMGEN classification

NTH

KD2_PFn_HIS_WHEN_CORRID

Selection criteria CORRID

Description

Specifies selection criteria based on CORRID. For example, if STC01 and STC02 were specified for CORRID, only data for threads with the specified correlation identifiers would be collected. To specify selection criteria, you can use the wildcard character *, which is for one or more characters, the suffix only, and the ?, which is for a single character.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

None

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

CORR(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P8

Panel field

CORRID

Default value

None

Batch parameter name

KD2_PF_HIS_WHEN_CORRID

PARMGEN name

KD2_PFnn_HIS_WHEN_CORRID

PARMGEN classification

NTH

KD2_PFnn_HIS_WHEN_ORIG

Selection criteria ORIGAUTHID

Description

Specifies selection criteria based on ORIGAUTHID. To specify selection criteria, you can use the wildcard character *, which is for one or more characters, the suffix only, and the ?, which is for a single character.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

None

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

ORIGAUTH(<value>)

In the Configuration Tool (ICAT)

Panel name

Near-Term History

Panel ID

KD261P8

Panel field

ORIGAUTHID

Default value

None

Batch parameter name

KD2_PF_HIS_WHEN_ORIG

PARMGEN name

KD2_PFnn_HIS_WHEN_ORIG

PARMGEN classification

NTH

KD2_PFn_HIS_WHEN_PLAN

Selection criteria PLANNAME

Description

Specifies selection criteria based on PLANNAME. For example, if CICSPR01 and CICSPR02 were specified for PLANNAME, only data for threads with the specified plannames would be collected.

To specify selection criteria, you can use the wildcard character *, which is for one or more characters, the suffix only, and the ?, which is for a single character.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

None

Location where the parameter value is stored

In the COPTssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

PLAN(<value>)

In the Configuration Tool (ICAT)**Panel name**

Near-Term History

Panel ID

KD261P8

Panel field

PLANNAME

Default value

None

Batch parameter name

KD2_PF_HIS_WHEN_PLAN

PARMGEN name

KD2_PFn_HIS_WHEN_PLAN

PARMGEN classification

NTH

KD2_PFn_THRDHIS_DYN_SQL

Collect dynamic SQL data

Description

This specifies whether dynamic SQL text and access path information is collected.

If Y is entered, the collector activates IFCIDs 22,63,105,107.

If F is entered, the collector activates IFCIDs 22,350,105,107. IFCID 350 records the complete text of a parsed SQL statement, while IFCID 63 is limited to the first 5000 bytes of a SQL statement.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

N

Permissible values

Y, N, F

Location where the parameter value is stored

In the COPTssid member of the *%RTE_HILEV%.%RTE_NAME%.RKD2PAR* library

KD2_PF_HIS_SEQ_VOLUME7

Output line

THRDSQL (<value>Y)

PARMGEN name

KD2_PFn_THRDHIS_DYN_SQL

PARMGEN classification

NTH

KD2_PFn_THRDHIS_LOCK_CNTN

Collect Lock contention data

Description

This specifies whether lock timeout and deadlock information is collected.

If Y is entered, the collector activates IFCIDs 172,196,105,107.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

THRDCONT (<value>Y)

PARMGEN name

KD2_PFn_THRDHIS_LOCK_CNTN

PARMGEN classification

NTH

KD2_PFn_THRDHIS_LOCK_SUSP

Collect lock suspension data

Description

This specifies whether lock wait information for local resources is collected.

If Y is entered, the collector activates IFCIDs 44,45,213,214,105,107.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

THRDSUSP (<value>Y)

PARMGEN name

KD2_PFn_THRDHIS_LOCK_SUSP

PARMGEN classification

NTH

KD2_PFn_THRDHIS_LOG_NUM

Number of Thread History VSAM datasets

Description

Specify the number of VSAM datasets to be used for Thread History collection for Enhanced 3270UI. You can specify 3 to 60. The default is 7.

This field is only applicable if you specified THVSAM, VSAMSEQTHVSAM, SEQTHVSAM, VSAMTHVSAM as the storage mechanism to be used for Near Term History.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

7

Minimum

3

Maximum

60

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

THRDLOG(<value>)

PARMGEN name

KD2_PFn_THRDHIS_LOG_NUM

PARMGEN classification

NTH

KD2_PFn_THRDHIS_SCAN_SUMM

Collect scan summary data

Description

This specifies whether scan data is collected.

If Y is entered, the collector activates IFCIDs 15,16,17,18.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

THRDSCAN(<value>Y)

PARMGEN name

KD2_PFn_THRDHIS_SCAN_SUMM

PARMGEN classification

NTH

KD2_PFn_THRDHIS_SORT_SUMM

Collect sort summary data

Description

This specifies whether sort data is collected.

If Y is entered, the collector activates IFCIDs 95 and 96.

Required or optional

Optional (Required in case KD2_PF_HIS_START is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the COPTssid member of the %RTE_HILEV%.%RTE_NAME%.RKD2PAR library

Output line

THRDSORT(<value>Y)

PARMGEN name

KD2_PFn_THRDHIS_SORT_SUMM

PARMGEN classification

NTH

Snapshot history (including DB2 Connect Monitoring)

This section lists the parameters for snapshot history (including DB2 Connect Monitoring).

Snapshot history data is useful, for example, if you want to examine activities leading to, and following, an exception without recreating the situation. The data is periodically stored by the OMEGAMON Collector in a wrap-around-managed snapshot history data set.

You can define how often the snapshots are stored by setting the sample interval time. The amount of stored snapshots depends on the snapshot data volume and the specified snapshot history data set size. When the defined maximum number of snapshots is exceeded, the oldest snapshot is deleted and the newest snapshot is added.

You can view this information through the history mode in the Performance Expert Client. This mode allows you to display recently stored snapshots at a specified point-in-time. You can then scroll forward and backward through the history of snapshot data to get a better understanding of what happened and to identify what caused the problem (for example, detected situations, bottlenecks, deadlocks, timeouts).

KD2_PFn_DCM_D2SHDCAI

DB2 Connect application data interval

Description

Specifies in seconds how often the OMEGAMON Collector is to collect DB2 Connect application data for later viewing. This value can be set from 10 second to 86400 seconds for one day. It is recommended to set this value to a multiple of KD2_PFn_SH_D2SHSTAI.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y and KD2_PF_DCM_D2SHDCAP is set to Y)

Default value

60

Minimum

10

Maximum

86400

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library**Output line**SHDB2CONNECTAPPLICATION=(*<KD2_PFnn_DCM_D2SHDCAP>*,*<value>*)**In the Configuration Tool (ICAT)****Panel name**

Snapshot History

Panel ID

KD261PE

Panel field

DB2 Connect Application Interval

Default value

60

Minimum

10

Maximum

86400

Batch parameter name

KD2_PF_DCM_D2SHDCAI

PARMGEN name

KD2_PFnn_DCM_D2SHDCAI

PARMGEN classification

SS_HIS

KD2_PFnn_DCM_D2SHDCAP

DB2 Connect Monitoring application data

Description

Specify whether DB2 Connect Monitoring application data is to be collected.

If you enable data collection for this collection then this enables the function DB2 Connect Monitoring.

Note: To use DB2 Connect Monitoring Performance Warehouse has to run at least once to set up the required tables for DB2 Connect Monitoring. Furthermore the DB2 Performance Expert Agent for DB2 Connect Monitoring Workstation has to be installed.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library**Output line**SHDB2CONNECTAPPLICATION=(*<value>*,*<KD2_PFnn_DCM_D2SHDCAI>*)**In the Configuration Tool (ICAT)****Panel name**

Snapshot History

KD2_PF_DCM_D2SHDCSI

Panel ID

KD261PE

Panel field

DB2 Connect Application

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_DCM_D2SHDCAP

PARMGEN name

KD2_PFn_DCM_D2SHDCAP

PARMGEN classification

SS_HIS

KD2_PFn_DCM_D2SHDCSI

DB2 Connect system data

Description

Specifies in seconds how often the OMEGAMON Collector is to collect DB2 Connect system data for later viewing. This value can be set from 10 second to 86400 seconds for one day. It is recommended to set this value to a multiple of KD2_PFn_SH_D2SHSTAI.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y and KD2_PF_DCM_D2SHDCST is set to Y)

Default value

120

Minimum

10

Maximum

86400

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SHDB2CONNECTSYSTEM=(<KD2_PFn_DCM_D2SHDCST>,<value>)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PE

Panel field

DB2 Connect System Interval

Default value

120

Minimum

10

Maximum

86400

Batch parameter name

KD2_PF_DCM_D2SHDCSI

PARMGEN name

KD2_PFn_DCM_D2SHDCSI

PARMGEN classification

SS_HIS

KD2_PFn_DCM_D2SHDCST

DB2 Connect system data

Description

Specify whether DB2 Connect Monitoring system data is to be collected.

If you enable data collection for this collection then this enables the function DB2 Connect Monitoring.

Note: To use DB2 Connect Monitoring Performance Warehouse has to run at least once to set up the required tables for DB2 Connect Monitoring. Furthermore the DB2 Performance Expert Agent for DB2 Connect Monitoring Workstation has to be installed.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SHDB2CONNECTSYSTEM=(<value> , <KD2_PFn_DCM_D2SHDCSI>)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PE

Panel field

DB2 Connect System

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_DCM_D2SHDCST

PARMGEN name

KD2_PFn_DCM_D2SHDCST

PARMGEN classification

SS_HIS

KD2_PFn_SH_D2SHDATA

Data set statistics data

Description

Specifies whether data set statistics data is collected.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y)

KD2_PF_SH_D2SHDATI

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

SHDATASETSTATISTICS=(*<value>*, <KD2_PFnn_SH_D2SHDATI>)

In the Configuration Tool (ICAT)

Panel name

Snapshot History

Panel ID

KD261PE

Panel field

Data Set Statistics

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_PF_SH_D2SHDATA

PARMGEN name

KD2_PFnn_SH_D2SHDATA

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SHDATI

Data set statistics interval

Description

Specifies in seconds how often the OMEGAMON Collector is to collect data set statistics data for later viewing. This value can be set from 1 second to 86400 seconds for one day.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y and KD2_PF_SH_D2SHDATA is set to Y)

Default value

300

Minimum

1

Maximum

86400

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

SHDATASETSTATISTICS=(<KD2_PFnn_SH_D2SHDATA>, *<value>*)

In the Configuration Tool (ICAT)

Panel name

Snapshot History

Panel ID

KD261PE

Panel field

Data Set Statistics Interval

Default value

300

Minimum

1

Maximum

86400

Batch parameter name

KD2_PF_SH_D2SHDATI

PARMGEN name

KD2_PFnn_SH_D2SHDATI

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SHKHST

Enable Snapshot history

Description

Used to specify whether Snapshot History data is to be collected.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

SNAPSHOTHISTORY=<value>

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PE

Panel field

Enable Snapshot history

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_SH_D2SHKHST

PARMGEN name

KD2_PFnn_SH_D2SHKHST

PARMGEN classification

SS_HIS

KD2_PFSH_D2SHLTHD

KD2_PFnn_SH_D2SHLTHD

Thread data including locking data

Description

Used to specify whether the collected thread data is to include locking data.

Required or optional

Optional (Required in case KD2_PFSH_D2SHKHST is set to Y and KD2_PFSH_D2SHTHDD is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SHTHREADLOCK=<value>

In the Configuration Tool (ICAT)

Panel name

Snapshot History

Panel ID

KD261PE

Panel field

Thread Include Locking

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PFSH_D2SHLTHD

PARMGEN name

KD2_PFnn_SH_D2SHLTHD

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SHSPAI

System parameters interval

Description

Specifies in seconds how often the OMEGAMON Collector is to collect system parameters data for later viewing. This value can be set from 1 second to 86400 seconds for one day.

Required or optional

Optional (Required in case KD2_PFSH_D2SHKHST is set to Y and KD2_PFSH_D2SHSPAR is set to Y)

Default value

300

Minimum

1

Maximum

86400

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SHSYSTEMPARAMETERS=(<KD2_PFn_SH_D2SHSPAR>,<value>)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PE

Panel field

System Parameters Interval

Default value

300

Minimum

1

Maximum

86400

Batch parameter name

KD2_PFn_SH_D2SHSPAI

PARMGEN name

KD2_PFn_SH_D2SHSPAI

PARMGEN classification

SS_HIS

KD2_PFn_SH_D2SHSPAR

System Parameters data

Description

Specifies whether system parameters data is collected.

Required or optional

Optional (Required in case KD2_PFn_SH_D2SHKHST is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SHSYSTEMPARAMETERS=(<value>,<KD2_PFn_SH_D2SHSPAI>)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PE

Panel field

System Parameters

Default value

Y

Permissible values

Y, N

KD2_PF_SH_D2SHSQLC

Batch parameter name

KD2_PF_SH_D2SHSPAR

PARMGEN name

KD2_PFnn_SH_D2SHSPAR

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SHSQLC

Dynamic Statement cache data

Description

Specifies whether dynamic statement cache data is collected.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SHSQLCACHE=(<value> , <KD2_PFnn_SH_D2SHSQLI>)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PE

Panel field

Dynamic Statement Cache

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_PF_SH_D2SHSQLC

PARMGEN name

KD2_PFnn_SH_D2SHSQLC

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SHSQLI

Dynamic statement cache interval

Description

Specifies in seconds how often the OMEGAMON Collector is to collect dynamic statement cache data for later viewing. This value can be set from 1 second to 86400 seconds for one day.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y and KD2_PF_SH_D2SHSQLC is set to Y)

Default value

300

Minimum

1

Maximum

86400

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library**Output line**

SHSQLCACHE=(<KD2_PFn_SH_D2SHSQLC>, <value>)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PE

Panel field

Dynamic Statement Cache Interval

Default value

300

Minimum

1

Maximum

86400

Batch parameter name

KD2_PFn_SH_D2SHSQLI

PARMGEN name

KD2_PFn_SH_D2SHSQLI

PARMGEN classification

SS_HIS

KD2_PFn_SH_D2SHSQLT

Thread data including statement text

Description

Used to specify whether thread data collected for Snapshot history is to include SQL statement text.

Required or optional

Optional (Required in case KD2_PFn_SH_D2SHKHST is set to Y and KD2_PFn_SH_D2SHTHDD is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library**Output line**

SHTHREADSQL=<value>

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PE

KD2_PF_SH_D2SHSSZE

Panel field

Thread Include Stmt Text

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_SH_D2SHSQLT

PARMGEN name

KD2_PFnn_SH_D2SHSQLT

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SHSSZE

Archive size

Description

Used to specify the maximum size of the Snapshot History data set. The specified value is the size of the data set in megabytes.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y)

Default value

16

Locations where the parameter value is stored**Location 1**

In the OMDDssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

MEGABYTES(<value>) -

Location 2

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SHDATASETSIZE=<value>

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PE

Panel field

Snaphshot history archive size

Default value

16

Batch parameter name

KD2_PF_SH_D2SHSSZE

PARMGEN name

KD2_PFnn_SH_D2SHSSZE

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SHSTAI

Statistics interval

Description

Specifies in seconds how often the OMEGAMON Collector is to collect statistics data for later viewing. This value can be set from 1 second to 86400 seconds for one day.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y and KD2_PF_SH_D2SHSTAT is set to Y)

Default value

120

Minimum

1

Maximum

86400

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SHSTATISTICS=(<KD2_PFnn_SH_D2SHSTAT>, <value>)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PE

Panel field

Statistics Interval

Default value

120

Minimum

1

Maximum

86400

Batch parameter name

KD2_PF_SH_D2SHSTAI

PARMGEN name

KD2_PFnn_SH_D2SHSTAI

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SHSTAT

Collect Statistics data

Description

Specifies whether statistics data is to be collected.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y)

Default value

N

Permissible values

Y, N

KD2_PF_SH_D2SHTHDD

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SHSTATISTICS=(<value>,<KD2_PFn_SH_D2SHSTAI>)

In the Configuration Tool (ICAT)

Panel name

Snapshot History

Panel ID

KD261PE

Panel field

Statistics

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_PF_SH_D2SHSTAT

PARMGEN name

KD2_PFn_SH_D2SHSTAT

PARMGEN classification

SS_HIS

KD2_PFn_SH_D2SHTHDD

Thread data

Description

Specified whether thread data 'without SQL text and locking information' is collected.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y)

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SHTHREAD=(<value>,<KD2_PFn_SH_D2SHTHDI>)

In the Configuration Tool (ICAT)

Panel name

Snapshot History

Panel ID

KD261PE

Panel field

Thread

Default value

Y

Permissible values

Y, N

Batch parameter name

KD2_Pf_SH_D2SHTHDD

PARMGEN name

KD2_Pfnn_SH_D2SHTHDD

PARMGEN classification

SS_HIS

KD2_Pfnn_SH_D2SHTHDI

Thread information interval

Description

Specifies in seconds how often the OMEGAMON Collector is to collect thread data for later viewing. This value can be set from 1 second to 86400 seconds for one day.

Required or optional

Optional (Required in case KD2_Pf_SH_D2SHKHST is set to Y and KD2_Pf_SH_D2SHTHDD is set to Y)

Default value

60

Minimum

1

Maximum

86400

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SHTHREAD=(<KD2_Pfnn_SH_D2SHTHDD>, <value>)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PE

Panel field

Thread Interval

Default value

60

Minimum

1

Maximum

86400

Batch parameter name

KD2_Pf_SH_D2SHTHDI

PARMGEN name

KD2_Pfnn_SH_D2SHTHDI

PARMGEN classification

SS_HIS

KD2_PFSH_D2SQCON1

KD2_PFnn_SH_D2SQCON1

Filter 1 DB2 connection ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional (Required in case KD2_PFSH_D2SHKHST is set to Y)

Default value

*

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

HQ1=(...,CN='<value>',...)

In the Configuration Tool (ICAT)

Panel name

Snapshot History

Panel ID

KD261PK

Panel field

Connection ID

Default value

*

Batch parameter name

KD2_PFSH_D2SQCON1

PARMGEN name

KD2_PFnn_SH_D2SQCON1

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQCON2

Filter 2 DB2 connection ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

HQ2=(...,CN='<value>',...)

In the Configuration Tool (ICAT)

Panel name

Snapshot History

Panel ID

KD261PK

Panel field

Connection ID

Default value

None

Batch parameter name

KD2_PF_SH_D2SQCON2

PARMGEN name

KD2_PFn_SH_D2SQCON2

PARMGEN classification

SS_HIS

KD2_PFn_SH_D2SQCON3

Filter 3 DB2 connection ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

HQ3=(... ,CN='<value>' ,...)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Connection ID

Default value

None

Batch parameter name

KD2_PF_SH_D2SQCON3

PARMGEN name

KD2_PFn_SH_D2SQCON3

PARMGEN classification

SS_HIS

KD2_PFn_SH_D2SQCON4

Filter 4 DB2 connection ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

KD2_PF_SH_D2SQCON5

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

HQ4=(... ,CN='<value>' ...)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Connection ID

Default value

None

Batch parameter name

KD2_PF_SH_D2SQCON4

PARMGEN name

KD2_PFnn_SH_D2SQCON4

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQCON5

Filter 5 DB2 connection ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

HQ5=(... ,CN='<value>',...)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Connection ID

Default value

None

Batch parameter name

KD2_PF_SH_D2SQCON5

PARMGEN name

KD2_PFnn_SH_D2SQCON5

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQCON6

Filter 6 DB2 connection ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

```
HQ6=(... ,CN='<value>' ,...)
```

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Connection ID

Default value

None

Batch parameter name

KD2_PF_SH_D2SQCON6

PARMGEN name

KD2_PFnn_SH_D2SQCON6

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQCOR1

Filter 1 DB2 correlation ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y)

Default value

*

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

```
HQ1=(... ,CR='<value>')
```

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

KD2_PF_SH_D2SQCOR2

Panel ID

KD261PK

Panel field

Correlation Name

Default value

*

Batch parameter name

KD2_PF_SH_D2SQCOR1

PARMGEN name

KD2_PFnn_SH_D2SQCOR1

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQCOR2

Filter 2 DB2 correlation ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

HQ2=(... ,CR='<value>')

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Correlation Name

Default value

None

Batch parameter name

KD2_PF_SH_D2SQCOR2

PARMGEN name

KD2_PFnn_SH_D2SQCOR2

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQCOR3

Filter 3 DB2 correlation ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library**Output line**

HQ3=(. . . ,CR='<value>')

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Correlation Name

Default value

None

Batch parameter name

KD2_PF_SH_D2SQCOR3

PARMGEN name

KD2_PFnn_SH_D2SQCOR3

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQCOR4

Filter 4 DB2 correlation ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library**Output line**

HQ4=(. . . ,CR='<value>')

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Correlation Name

Default value

None

Batch parameter name

KD2_PF_SH_D2SQCOR4

KD2_PFn_SH_D2SQCOR5

PARMGEN name

KD2_PFn_SH_D2SQCOR4

PARMGEN classification

SS_HIS

KD2_PFn_SH_D2SQCOR5

Filter 5 DB2 correlation ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

HQ5=(. . . ,CR='<value>')

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Correlation Name

Default value

None

Batch parameter name

KD2_PFn_SH_D2SQCOR5

PARMGEN name

KD2_PFn_SH_D2SQCOR5

PARMGEN classification

SS_HIS

KD2_PFn_SH_D2SQCOR6

Filter 6 DB2 correlation ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

HQ6=(. . . ,CR='<value>')

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Correlation ID

Default value

None

Batch parameter name

KD2_PF_SH_D2SQCOR6

PARMGEN name

KD2_PFnn_SH_D2SQCOR6

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQPLA1

Filter 1 DB2 Plan name

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y)

Default value

*

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

HQ1=(... , PL='<value>' , ...)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

DB2 Plan Name

Default value

*

Batch parameter name

KD2_PF_SH_D2SQPLA1

PARMGEN name

KD2_PFnn_SH_D2SQPLA1

PARMGEN classification

SS_HIS

KD2_PF_SH_D2SQPLA2

KD2_PFnn_SH_D2SQPLA2

Filter 2 DB2 Plan name

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

HQ2=(...,PL='<value>',...)

In the Configuration Tool (ICAT)

Panel name

Snapshot History

Panel ID

KD261PK

Panel field

DB2 Plan Name

Default value

None

Batch parameter name

KD2_PF_SH_D2SQPLA2

PARMGEN name

KD2_PFnn_SH_D2SQPLA2

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQPLA3

Filter 3 DB2 Plan name

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

HQ3=(...,PL='<value>',...)

In the Configuration Tool (ICAT)

Panel name

Snapshot History

Panel ID

KD261PK

Panel field

DB2 Plan Name

Default value

None

Batch parameter name

KD2_Pf_SH_D2SQPLA3

PARMGEN name

KD2_Pfnn_SH_D2SQPLA3

PARMGEN classification

SS_HIS

KD2_Pfnn_SH_D2SQPLA4

Filter 4 DB2 Plan name

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

```
HQ4=(... ,PL='<value>' ,...)
```

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

DB2 Plan Name

Default value

None

Batch parameter name

KD2_Pf_SH_D2SQPLA4

PARMGEN name

KD2_Pfnn_SH_D2SQPLA4

PARMGEN classification

SS_HIS

KD2_Pfnn_SH_D2SQPLA5

Filter 5 DB2 Plan name

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

KD2_PF_SH_D2SQPLA6

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

HQ5=(... ,PL='<value>' ,...)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

DB2 Plan Name

Default value

None

Batch parameter name

KD2_PF_SH_D2SQPLA5

PARMGEN name

KD2_PFnn_SH_D2SQPLA5

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQPLA6

Filter 6 DB2 Plan name

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

HQ6=(... ,PL='<value>' ,...)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

DB2 Plan Name

Default value

None

Batch parameter name

KD2_PF_SH_D2SQPLA6

PARMGEN name

KD2_PFnn_SH_D2SQPLA6

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQPRI1

Filter 1 Primary AUTH ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional (Required in case KD2_PF_SH_D2SHKHST is set to Y)

Default value

*

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

HQ1=(PR='<value>' . . .

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Primary AUTH ID

Default value

*

Batch parameter name

KD2_PF_SH_D2SQPRI1

PARMGEN name

KD2_PFnn_SH_D2SQPRI1

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQPRI2

Filter 2 Primary AUTH ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

HQ2=(PR='<value>', . . .)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

KD2_PF_SH_D2SQPRI3

Panel ID

KD261PK

Panel field

Primary AUTH ID

Default value

None

Batch parameter name

KD2_PF_SH_D2SQPRI2

PARMGEN name

KD2_PFnn_SH_D2SQPRI2

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQPRI3

Filter 3 Primary AUTH ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

HQ3=(PR='<value>',...)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Primary AUTH ID

Default value

None

Batch parameter name

KD2_PF_SH_D2SQPRI3

PARMGEN name

KD2_PFnn_SH_D2SQPRI3

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQPRI4

Filter 4 Primary AUTH ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library**Output line**

HQ4=(PR='<value>',...)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Primary AUTH ID

Default value

None

Batch parameter name

KD2_PF_SH_D2SQPRI4

PARMGEN name

KD2_PFnn_SH_D2SQPRI4

PARMGEN classification

SS_HIS

KD2_PFnn_SH_D2SQPRI5

Filter 5 Primary AUTH ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library**Output line**

HQ5=(PR='<value>',...)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Primary AUTH ID

Default value

None

Batch parameter name

KD2_PF_SH_D2SQPRI5

KD2_PFn_SH_D2SQPRI6

PARMGEN name

KD2_PFn_SH_D2SQPRI5

PARMGEN classification

SS_HIS

KD2_PFn_SH_D2SQPRI6

Filter 6 Primary AUTH ID

Description

Specify a qualifier or wildcard character to take the default. Any qualifiers that are not specified are set to an asterisk.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

HQ6=(PR='<value>',...)

In the Configuration Tool (ICAT)**Panel name**

Snapshot History

Panel ID

KD261PK

Panel field

Primary AUTH ID

Default value

None

Batch parameter name

KD2_PFn_SH_D2SQPRI6

PARMGEN name

KD2_PFn_SH_D2SQPRI6

PARMGEN classification

SS_HIS

DB2 Explain

This section lists the parameters for DB2 Explain.

Explain functions provide an easy-to-read representation of access plan information for your SQL queries and statements. You can use this information to decide how to tune your queries. The built-in explain functions are Easy Explain and the EXPLAIN report.

Note: You must create a database to be used by EXPLAIN. There are no special requirements regarding database name, storage group, or index buffer pool. But you must use an 8 KB buffer pool. The database name has to be specified using the PARMGEN.

KD2_PFn_EX_D2EXACT

Enable DB2 EXPLAIN

Description

Specify whether you want to enable DB2 EXPLAIN:

Y

Enable DB2 EXPLAIN.

N

Disable DB2 EXPLAIN.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)**Panel name**

DB2 Explain

Panel ID

KD261P4

Panel field

Enable DB2 EXPLAIN

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_Pf_EX_D2EXACT

PARMGEN name

KD2_Pfnn_EX_D2EXACT

PARMGEN classification

EXPLAIN

KD2_Pfnn_EX_D2EXDB

DB2 EXPLAIN data base

Description

Specify the EXPLAIN database name. There are no special requirements regarding database name, storage group, or index buffer pool. But you must use an 8 KB buffer pool.

Required or optional

Optional (Required in case KD2_Pf_EX_D2EXACT is set to Y)

Default value

DATBA8K

Locations where the parameter value is stored**Location 1**In the EXCTssid member of the *rhilev.midlev.rtename*.RKD2SAM library**Output line**

IN DATABASE <value>

Location 2In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library**Output line**

GRANT CREATETS ON DATABASE <value> TO <KD2_Pfnn_EX_D2EXOBJ>

KD2_PFn_EX_D2EXOBJ

Location 3

In the EXGRssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
GRANT CREATETAB ON DATABASE <value> TO <KD2_PFn_EX_D2EXOBJ>
```

Location 4

In the EXCQssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
IN DATABASE <value>
```

In the Configuration Tool (ICAT)

Panel name

DB2 Explain

Panel ID

KD261P4

Panel field

EXPLAIN database

Default value

DATBA8K

Batch parameter name

KD2_PFn_EX_D2EXDB

PARMGEN name

KD2_PFn_EX_D2EXDB

PARMGEN classification

EXPLAIN

KD2_PFn_EX_D2EXOBJ

DB2 EXPLAIN objects owner

Description

Specify the AUTH ID of the OMEGAMON XE for DB2 PE started task.

Required or optional

Optional (Required in case KD2_PFn_EX_D2EXACT is set to Y)

Default value

DB2PM

Locations where the parameter value is stored

Location 1

In the EXBDssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
OWNER (<value>) +
```

Location 2

In the EXGRssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
GRANT SELECT ON SYSIBM.SYSPLAN TO <value>;
```

Location 3

In the EXGRssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
GRANT SELECT ON SYSIBM.SYSSTMT TO <value>;
```

Location 4

In the EXGRssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
GRANT SELECT ON SYSIBM.SYSTABLES TO <value>;
```

Location 5

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSPACKSTMT TO <value>;
```

Location 6

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSINDEXES TO <value>;
```

Location 7

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSTABLEPART TO <value>;
```

Location 8

In the EXC8ssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
SET CURRENT SQLID = '<value>;
```

Location 9

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSINDEXPART TO <value>;
```

Location 10

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSPACKAGE TO <value>;
```

Location 11

In the EXGPssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON TABLE <value>..DGO_SYSDBRM TO %exuser%;
```

Location 12

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT CREATETS ON DATABASE <KD2_PFn_EX_D2EXDB> TO <value>;
```

Location 13

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSTABLESPACE TO <value>;
```

Location 14

In the EXGPssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT INSERT ON TABLE <value>..DGO_SYSPACKAGE TO %exuser%;
```

Location 15

In the EXCQssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
SET CURRENT SQLID = '<value>;
```

Location 16

In the EXC0ssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
SET CURRENT SQLID = '<value>';
```

Location 17

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSKEYS TO <value>;
```

Location 18

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSINDEXSTATS TO <value>;
```

Location 19

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSPACKDEP TO <value>;
```

Location 20

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSTABSTATS TO <value>;
```

Location 21

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSCOLUMNS TO <value>;
```

Location 22

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT CREATETAB ON DATABASE <KD2_Pfnn_EX_D2EXDB> TO <value>;
```

Location 23

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT PACKADM ON COLLECTION K02EX510 TO <value>;
```

Location 24

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT USE OF STOGROUP SYSDEFLT TO <value>;
```

Location 25

In the EXCVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
SET CURRENT SQLID = '<value>';
```

Location 26

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSDATABASE TO <value>;
```

Location 27

In the EXDVssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
SET CURRENT SQLID = '<value>';
```

Location 28

In the EXGPssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON TABLE <value>..DGO_SYSPACKAGE TO %exuser%;
```

Location 29

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSCOLDIST TO <value>;
```

Location 30

In the EXCTssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
SET CURRENT SQLID = '<value>';
```

Location 31

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSFIELDS TO <value>;
```

Location 32

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSDBRM TO <value>;
```

Location 33

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSSYNONYMS TO <value>;
```

Location 34

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON SYSIBM.SYSPACKLIST TO <value>;
```

Location 35

In the EXGPssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT INSERT ON TABLE <value>..DGO_SYSDBRM TO %exuser%;
```

Location 36

In the EXBPssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
OWNER (<value>) +
```

Location 37

In the EXGRssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT BINDADD TO <value>;
```

In the Configuration Tool (ICAT)**Panel name**

DB2 Explain

Panel ID

KD261P4

Panel field

Owner of EXPLAIN objects

Default value

DB2PM

KD2_Pf_EX_D2EXQMF

Batch parameter name

KD2_Pf_EX_D2EXOBJ

PARMGEN name

KD2_Pfnn_EX_D2EXOBJ

PARMGEN classification

EXPLAIN

KD2_Pfnn_EX_D2EXQMF

Is DB2 EXPLAIN QMF installed

Description

Specify Y if QMF is installed.

Required or optional

Optional (Required in case KD2_Pf_EX_D2EXACT is set to Y)

Default value

N

Permissible values

Y, N

Locations where the parameter value is stored**Location 1**

In the EXGPssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
GRANT SELECT ON <value>I..OBJECT_DATA TO %exuser%;
```

Location 2

In the EXCQssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
FROM <value>I..OBJECT_DIRECTORY ;
```

Location 3

In the EXGPssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
GRANT SELECT ON <value>I..OBJECT_DIRECTORY TO %exuser%;
```

Location 4

In the EXCQssid member of the *rhilev.midlev.rtename.RKD2SAM* library

Output line

```
FROM <value>I..OBJECT_DATA ;
```

In the Configuration Tool (ICAT)**Panel name**

DB2 Explain

Panel ID

KD261P4

Panel field

Is QMF installed

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_Pf_EX_D2EXQMF

PARMGEN name

KD2_PFnn_EX_D2EXQMF

PARMGEN classification

EXPLAIN

KD2_PFnn_EX_D2EXQMFI

DB2 QMF Owner ID

Description

If QMF is installed, specify the QMF Owner ID.

Required or optional

Optional (Required in case KD2_PF_EX_D2EXACT is set to Y and KD2_PF_EX_D2EXQMF is set to Y)

Default value

Q

Locations where the parameter value is stored**Location 1**

In the EXGPssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON <value>..OBJECT_DIRECTORY TO %exuser%;
```

Location 2

In the EXCQssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
FROM <value>..OBJECT_DIRECTORY ;
```

Location 3

In the EXCQssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
FROM <value>..OBJECT_DATA ;
```

Location 4

In the EXGPssid member of the *rhilev.midlev.rtename*.RKD2SAM library

Output line

```
GRANT SELECT ON <value>..OBJECT_DATA TO %exuser%;
```

In the Configuration Tool (ICAT)**Panel name**

DB2 Explain

Panel ID

KD261P4

Panel field

QMF Owner ID

Default value

Q

Batch parameter name

KD2_PF_EX_D2EXQMFI

PARMGEN name

KD2_PFnn_EX_D2EXQMF

PARMGEN classification

EXPLAIN

DB2 SQL Performance Analyzer

This section lists all configuration parameters provided for DB2 SQL Performance Analyzer.

DB2 SQL Performance Analyzer provides you with an extensive analysis of SQL queries without executing them. This analysis helps you in tuning your queries to achieve maximum performance. DB2 SQL Performance Analyzer can analyze new access paths, determine if action is needed, and estimate the costs of new paths in database resources consumed.

With DB2 SQL Performance Analyzer you can reduce the escalating costs of database queries by estimating their cost prior to execution. It delivers an Easy Explain function that provides an alternate view of the Explain data. Comparison of old and new plans is supported, along with Retro-Explain for Access plans, helping you to find out how long queries will take and to prevent queries from running too long. It can also aid in the migration of catalog statistics to test machines for in-depth analysis of production applications.

KD2_PFnn_SQLPA_CF_ANLC

Fully qualified SQL PA ANLC config

Description

Specify the fully qualified SQL PA ANL Control configuration.

Required or optional

Optional (Required in case KD2_PF_SQLPA_ENABLE is set to Y and KD2_PF_SQLPA_CF_ENBL is set to Y)

Default value

SYS1.DB2.SQLPA(ANLC)

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SQLPAANLCNTL=<value>

In the Configuration Tool (ICAT)

Panel name

SQL Performance Analyzer

Panel ID

KD261PQ

Panel field

ANL Control

Default value

None

Batch parameter name

KD2_PF_SQLPA_CF_ANLC

PARMGEN name

KD2_PFnn_SQLPA_CF_ANLC

PARMGEN classification

SQLPA

KD2_PFnn_SQLPA_CF_ANLP

Fully qualified SQL PA ANLP config

Description

Specify the fully qualified SQL PA ANL Parm configuration.

Required or optional

Optional (Required in case KD2_PF_SQLPA_ENABLE is set to Y and KD2_PF_SQLPA_CF_ENBL is set to Y)

Default value

SYS1.DB2.SQLPA(ANLP)

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

SQLPAANLPARM=<value>

In the Configuration Tool (ICAT)**Panel name**

SQL Performance Analyzer

Panel ID

KD261PQ

Panel field

ANL Parm

Default value

None

Batch parameter name

KD2_PF_SQLPA_CF_ANLP

PARMGEN name

KD2_PFnn_SQLPA_CF_ANLP

PARMGEN classification

SQLPA

KD2_PFnn_SQLPA_CF_ENBL

Enable use of SQL PA configuration

Description

Used to specify whether an existent SQL Performance Analyzer configuration is to be used:

Y

The SQL Performance Analyzer configuration is used.

N

The SQL Performance Analyzer configuration is not used.

In version 520 and above, this parameter must be set to Y.

Required or optional

Optional (Required in case KD2_PF_SQLPA_ENABLE is set to Y)

Default value

Y

Permissible values

Y

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)**Panel name**

SQL Performance Analyzer

Panel ID

KD261PQ

KD2_PF_SQLPA_ENABLE

Panel field

Use existing SQL Performance Analyzer configuration

Default value

Y

Permissible values

Y

Batch parameter name

KD2_PF_SQLPA_CF_ENBL

PARMGEN name

KD2_PFnn_SQLPA_CF_ENBL

PARMGEN classification

SQLPA

KD2_PFnn_SQLPA_ENABLE

Enable SQL Performance Analyzer

Description

Used to specify whether the SQL Performance Analyzer is to be configured. Specify one of the following values:

Y

The SQL Performance Analyzer is to be configured.

N

The SQL Performance Analyzer is not to be configured.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)

Panel name

SQL Performance Analyzer

Panel ID

KD261PQ

Panel field

Enable SQL Performance Analyzer

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_SQLPA_ENABLE

PARMGEN name

KD2_PFnn_SQLPA_ENABLE

PARMGEN classification

SQLPA

KD2_PFnn_SQLPA_STEPDSN

Fully qualified SQL PA STEPLIB dsn

Description

Specify the fully qualified SQL PA STEPLIB data set name. Refer to the IBM DB2 SQL Performance Analyzer for z/OS Installation Guide for detailed installation and customization information.

Required or optional

Optional (Required in case KD2_PF_SQLPA_ENABLE is set to Y)

Default value

SYS1.DB2.SQLPA

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

SQLPASTEPLIB=<value>

In the Configuration Tool (ICAT)**Panel name**

SQL Performance Analyzer

Panel ID

KD261PQ

Panel field

Dataset name

Default value

None

Batch parameter name

KD2_PF_SQLPA_STEPDSN

PARMGEN name

KD2_PFnn_SQLPA_STEPDSN

PARMGEN classification

SQLPA

KD2_PFnn_SQLPA_VERSION

DB2 version for SQLPA

Description

This is the version of the SQL Performance Analyzer. Valid values are 4.2 and 5.1

Required or optional

Optional (Required in case KD2_PF_SQLPA_ENABLE is set to Y)

Default value

5.1

Permissible values

4.2, 5.1

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename*.RKD2PAR library

Output line

SQLPAVERSION=<value>

In the Configuration Tool (ICAT)**Panel name**

SQL Performance Analyzer

KD2_PF_TRACES_318

Panel ID

KD261PQ

Panel field

Version

Default value

5.1

Permissible values

4.2, 5.1

Batch parameter name

KD2_PF_SQLPA_VERSION

PARMGEN name

KD2_PFn SQLPA_VERSION

PARMGEN classification

SQLPA

Additional DB2 traces

This section lists the parameters for additional DB2 traces.

You can specify additional DB2 trace commands to be started automatically when OMEGAMON XE for DB2 PE starts. Use the following parameters to provide valid **START TRACE** commands. Note that when OMEGAMON XE for DB2 PE/OMEGAMON XE for DB2 PM shuts down, the traces are not stopped.

KD2_PFn_TRACES_318

Start IFCID 318

Description

Used to specify whether a start trace command should be issued for IFCID 318. IFCID 318 is a switch that causes DB2 to collect detailed information on SQL statements in the dynamic statement cache. The collected information is externalized by means of IFCID 316.

If you set 'Enable end-to-end SQL monitoring support' (KD2_OMPE_E2E_MON_SPRT) to Y, IFCID 318 must be set to Y.

Note: Dynamic statement cache data collection is only available for DB2 Version 8 and higher. If you intend to use end-to-end SQL monitoring dynamic statement cache data collection is required. Make sure to set this flag to Y.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)**Panel name**

Start Additional DB2 Traces

Panel ID

KD2PTRAC

Panel field

IFCID 318 (Dynamic SQL statement cache)

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_TRACES_318

PARMGEN name

KD2_PFnn_TRACES_318

PARMGEN classification

DB2

KD2_PFnn_TRACES_400

Start IFCID 400

Description

Used to specify whether a start trace command should be issued for IFCID 400. IFCID 400 is a switch that causes DB2 to collect detailed information on static SQL statement in the EDM pool. The collected information is externalized by means of IFCID 401. The default is N.

If you set 'Enable end-to-end SQL monitoring support' (KD2_OMPE_E2E_MON_SPRT) to Y, IFCID 400 must be set to Y.

Note: Static statement data collection is only available for DB2 Version 10. If you intend to use end-to-end SQL monitoring static SQL statement data collection is required. Make sure to set this flag to Y.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

This value is not stored in a configuration member.

In the Configuration Tool (ICAT)**Panel name**

Start Additional DB2 Traces

Panel ID

KD2PTRAC

Panel field

IFCID 400 (Static SQL statement cache)

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_TRACES_400

PARMGEN name

KD2_PFnn_TRACES_400

PARMGEN classification

DB2

KD2_PFnn_TRACES_DB2CMD2

DB2 Command 2

Description

You can enter any valid DB2 command in this field. For each DB2 subsystem that is monitored by the OEMGAMON Collector a PE Server subtask is started. The DB2 command specified here is issued as part of the start sequence of the PE Server subtask.

Note: Your input for these fields is not validated. You have to make sure that you enter a valid DB2 command. If the DB2 command is not correct the return code is written to the SYSPRINT of the OMEGAMON Collector at startup.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

DB2COMMAND= '<value>'

In the Configuration Tool (ICAT)**Panel name**

Start Additional DB2 Traces

Panel ID

KD2PTRAC

Panel field

DB2 command

Default value

None

Batch parameter name

KD2_PF_TRACES_DB2CMD2

PARMGEN name

KD2_PFnn_TRACES_DB2CMD2

PARMGEN classification

DB2

KD2_PFnn_TRACES_DB2CMD3

DB2 Command 3

Description

You can enter any valid DB2 command in this field. For each DB2 subsystem that is monitored by the OEMGAMON Collector a PE Server subtask is started. The DB2 command specified here is issued as part of the start sequence of the PE Server subtask.

Note: Your input for these fields is not validated. You have to make sure that you enter a valid DB2 command. If the DB2 command is not correct the return code is written to the SYSPRINT of the OMEGAMON Collector at startup.

Required or optional

Optional

Default value

None

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

DB2COMMAND= '<value>'

In the Configuration Tool (ICAT)**Panel name**

Start Additional DB2 Traces

Panel ID

KD2PTRAC

Panel field

DB2 command

Default value

None

Batch parameter name

KD2_PF_TRACES_DB2CMD3

PARMGEN name

KD2_PFnn_TRACES_DB2CMD3

PARMGEN classification

DB2

KD2_PFnn_TRACES_DB2CMD4

DB2 Command 4

Description

You can enter any valid DB2 command in this field. For each DB2 subsystem that is monitored by the OEMGAMON Collector a PE Server subtask is started. The DB2 command specified here is issued as part of the start sequence of the PE Server subtask.

Note:Your input for these fields is not validated. You have to make sure that you enter a valid DB2 command. If the DB2 command is not correct the return code is written to the SYSPRINT of the OMEGAMON Collector at startup.

Required or optional

Optional

Default value

None

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

DB2COMMAND= '<value>'

In the Configuration Tool (ICAT)**Panel name**

Start Additional DB2 Traces

Panel ID

KD2PTRAC

Panel field

DB2 command

Default value

None

Batch parameter name

KD2_PF_TRACES_DB2CMD4

PARMGEN name

KD2_PFnn_TRACES_DB2CMD4

PARMGEN classification

DB2

Additional monitoring features

This section lists the parameters for additional monitoring features.

This section contains parameters to enable additional monitoring features. These include DB2 message monitoring and Stored Procedure monitoring.

KD2_PFn ACS_DB2MSGMON

Starts the DB2 message monitor

Description

If Y is specified the DB2 message monitor is started.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

DB2MSGMON=<value>

In the Configuration Tool (ICAT)**Panel name**

Additional Settings

Panel ID

KD2PPFAC

Panel field

Start DB2 message monitoring

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_ACS_DB2MSGMON

PARMGEN name

KD2_PFn ACS_DB2MSGMON

PARMGEN classification

READA

KD2_PFn_READA_OPBUFSIZE

The size of the OP buffer

Description

The size of the OP buffer used by the READA collector task to collect DB2 IFCIDs for all monitoring functions. The default value is 16 MB. The value is customizable between 16 and 64 MB.

Required or optional

Required

Default value

16

Minimum

16

Maximum

64

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

RACOPSIZE=<value>

In the Configuration Tool (ICAT)**Panel name**

Additional Settings

Panel ID

KD2PPFAC

Panel field

OP Buffer Size

Default value

16

Minimum

16

Maximum

64

Batch parameter name

KD2_PF_READA_OPBUFSIZE

PARMGEN name

KD2_PFnn_READA_OPBUFSIZE

PARMGEN classification

READA

KD2_PFnn_READA_OPBUFTHR

The threshold for the OP buffer POST evt

Description

The threshold used to fire a POST event to the READA collector task. The threshold specifies the percentage of the OP buffer size that can be buffered before the monitor program ECB is posted. The ECB is posted when the amount of trace data collected has reached the value that is specified in the byte count field.

Required or optional

Required

Default value

6

Minimum

5

Maximum

75

Location where the parameter value is storedIn the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library**Output line**

RACOPTHSHLD=<value>

KD2_PF_READA_SPMON

In the Configuration Tool (ICAT)

Panel name

Additional Settings

Panel ID

KD2PPFAC

Panel field

OP Buffer POST Threshold

Default value

5

Minimum

5

Maximum

75

Batch parameter name

KD2_PF_READA_OPBUFTHR

PARMGEN name

KD2_PFnn_READA_OPBUFTHR

PARMGEN classification

READA

KD2_PFnn_READA_SPMON

Starts the Stored Procedure monitor

Description

If Y is specified the SP monitor is started. The READA collector task is not started by default. However, if the SP monitor is activated the READA collector task gets automatically started. By starting the SP monitor, other monitor functions in the READA collectors task are not influenced. If the SP monitor is stopped and no other monitor function is started in the READA collector task, then the READA collector task is also stopped. When activating the SP monitor a DB2 trace command is started.

Required or optional

Required

Default value

N

Permissible values

Y, N

Location where the parameter value is stored

In the OMPEssid member of the *rhilev.midlev.rtename.RKD2PAR* library

Output line

SPMON=<value>

In the Configuration Tool (ICAT)

Panel name

Additional Settings

Panel ID

KD2PPFAC

Panel field

Start DB2 message monitoring

Default value

N

Permissible values

Y, N

Batch parameter name

KD2_PF_READA_SPMON

PARMGEN name

KD2_PFnn_READA_SPMON

PARMGEN classification

READA

Product legal notices

This information was developed for products and services offered in the U.S.A.

This material may be available from IBM in other languages. However, you may be required to own a copy of the product or product version in that language in order to access it.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive Armonk, NY 10504-1785 U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Director of Licensing IBM Corporation North Castle Drive Armonk, NY 10504-1785 U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated

through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work, must include a copyright notice as follows:

© (your company name) (year). Portions of this code are derived from IBM Corp. Sample Programs. © Copyright IBM Corp. _enter the year or years_. All rights reserved.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Programming interface information

This publication documents intended Programming Interfaces that allow the customer to write programs to obtain the services of OMEGAMON for Db2 Performance Expert.

This publication documents information that is NOT intended to be used as Programming Interfaces of OMEGAMON for Db2 Performance Expert.

This publication primarily documents intended Programming Interfaces that allow the customer to write programs to obtain the services of OMEGAMON for Db2 Performance Expert.

This publication also documents information that is NOT intended to be used as Programming Interfaces of OMEGAMON for Db2 Performance Expert. This information is identified where it occurs by an introductory statement to a topic or section.

This publication primarily documents information that is NOT intended to be used as Programming Interfaces of OMEGAMON for Db2 Performance Expert.

This publication also documents intended Programming Interfaces that allow the customer to write programs to obtain the services of OMEGAMON for Db2 Performance Expert. This information is identified where it occurs by an introductory statement to a topic or section.

Trademarks

IBM, the IBM logo, and [ibm.com](http://www.ibm.com)® are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at "Copyright and trademark information" at <http://www.ibm.com/legal/copytrade.html>.

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

Intel, Intel logo, Intel Inside, Intel Inside logo, Intel Centrino, Intel Centrino logo, Celeron, Xeon, Intel SpeedStep, Itanium, and Pentium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Java™ and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Linux® is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, and service names may be trademarks or service marks of others.

Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions:

Applicability: These terms and conditions are in addition to any terms of use for the IBM website.

Personal use: You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

Commercial use: You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

Rights: Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

Privacy policy considerations

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth below.

This Software Offering does not use cookies or other technologies to collect personally identifiable information.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at <http://www.ibm.com/privacy> and the section titled "Cookies, Web Beacons, and Other Technologies" in IBM's Online Privacy Statement at <http://www.ibm.com/privacy/details>. Also, see the "IBM Software Products and Software-as-a-Service Privacy Statement" at <http://www.ibm.com/software/info/product-privacy>.

Index

A

accessibility features [2](#)

B

basic product [5](#)

Batch parameters

[KD2_CLA_DB2ID_DFLT 14](#)
[KD2_CLA_LROWS 17](#)
[KD2_CLA_MVS_SYSID 18](#)
[KD2_CLA_SEC_AUTH_CLAS 16](#)
[KD2_CLA_STC 8](#)
[KD2_CLA_UMAX 19](#)
[KD2_CLA_USER 19](#)
[KD2_CLA_VTM_APPL_LOGON 20](#)
[KD2_CLA_VTM_NODE 20](#)
[KD2_OMPE_AUTH_FAIL 21](#)
[KD2_OMPE_AUTODETECT 22](#)
[KD2_OMPE_CCPC_TIMER 23](#)
[KD2_OMPE_CCPC_TRACE 24](#)
[KD2_OMPE_CF_REBUILT 24](#)
[KD2_OMPE_CHECKSYS 25](#)
[KD2_OMPE_CPU_PARALLEL 26](#)
[KD2_OMPE_DB2_EVENT 27](#)
[KD2_OMPE_DB2_EXIT 27](#)
[KD2_OMPE_DB2_USER 28](#)
[KD2_OMPE_DB2EXIT 8](#)
[KD2_OMPE_DB2LOADLIB_V10 9](#)
[KD2_OMPE_DB2LOADLIB_V11 10](#)
[KD2_OMPE_DB2LOADLIB_V12 11](#)
[KD2_OMPE_DB2RUNLIB_V10 11](#)
[KD2_OMPE_DB2RUNLIB_V11 12](#)
[KD2_OMPE_DB2RUNLIB_V12 13](#)
[KD2_OMPE_DEADLOCK 29](#)
[KD2_OMPE_DSHLQ 30](#)
[KD2_OMPE_DSN_EXTENT 31](#)
[KD2_OMPE_DSP_SIZE 31](#)
[KD2_OMPE_E2E_MON_SVRT 32](#)
[KD2_OMPE_EDMP_FULL 33](#)
[KD2_OMPE_EXTENT_THOLD 34](#)
[KD2_OMPE_GLOBAL_TRACE 34](#)
[KD2_OMPE_GRANT_AGUSER 35](#)
[KD2_OMPE_GRANT_EXUSER 35](#)
[KD2_OMPE_GRANT_PEUSER 36](#)
[KD2_OMPE_GRANT_PWUSER 36](#)
[KD2_OMPE_ISPF_LANG 37](#)
[KD2_OMPE_LOGSPACE 37](#)
[KD2_OMPE_MAX_SESSIONS 38](#)
[KD2_OMPE_MGMTCLAS 39](#)
[KD2_OMPE_PE_SUPPORT 40](#)
[KD2_OMPE_RUNALLOC 41](#)
[KD2_OMPE_SHRD_PRFLIB 41](#)
[KD2_OMPE_STOCLAS 42](#)
[KD2_OMPE_SUB_D2PADASP 43](#)
[KD2_OMPE_SUB_D2PAGRPN 44](#)
[KD2_OMPE_SUB_D2PARCVT 44](#)

Batch parameters (*continued*)

[KD2_OMPE_SUB_D2PASSIT 45](#)
[KD2_OMPE_SUB_D2PATSEC 46](#)
[KD2_OMPE_SUB_D2PAXCFT 47](#)
[KD2_OMPE_SYSAFF 48](#)
[KD2_OMPE_TCPIP_ADDRESS 48](#)
[KD2_OMPE_TCPIP_NAME 49](#)
[KD2_OMPE_THREAD_COMMIT 50](#)
[KD2_OMPE_TIMEOUT 50](#)
[KD2_OMPE_TRACE_LEVEL 51](#)
[KD2_OMPE_UNIT 52](#)
[KD2_OMPE_UR 53](#)
[KD2_OMPE_USE_MODEL 53](#)
[KD2_OMPE_VOLUME 54](#)
[KD2_OMPE_VSAM_MGMTCLAS 56](#)
[KD2_OMPE_VSAM_STOCLAS 56](#)
[KD2_OMPE_VSAM_VOLUME 57](#)
[KD2_PF_ACS_DB2MSGMON 220](#)
[KD2_PF_AEXCP_D2PYACT 89](#)
[KD2_PF_AEXCP_D2TPFDSN 89](#)
[KD2_PF_AEXCP_D2TPFDSP 90](#)
[KD2_PF_AEXCP_D2TPFFLG 91](#)
[KD2_PF_AEXCP_D2TPINTV 92](#)
[KD2_PF_AEXCP_D2TPLDSN 92](#)
[KD2_PF_AEXCP_D2TPLDSP 93](#)
[KD2_PF_AEXCP_D2TPLFLG 94](#)
[KD2_PF_AEXCP_D2TPTDSN 95](#)
[KD2_PF_AEXCP_D2TPTFMC 96](#)
[KD2_PF_AEXCP_D2TPTFSC 96](#)
[KD2_PF_AEXCP_D2TPUID 97](#)
[KD2_PF_AEXCP_D2TPUXIT 98](#)
[KD2_PF_AEXCP_D2TPVL 98](#)
[KD2_PF_DCM_D2SHDCAI 177](#)
[KD2_PF_DCM_D2SHDCAP 178](#)
[KD2_PF_DCM_D2SHDCSI 178](#)
[KD2_PF_DCM_D2SHDCST 179](#)
[KD2_PF_EX_D2EXACT 205](#)
[KD2_PF_EX_D2EXDB 206](#)
[KD2_PF_EX_D2EXOBJ 210](#)
[KD2_PF_EX_D2EXQMF 210](#)
[KD2_PF_EX_D2EXQMFI 211](#)
[KD2_PF_HIS_BUFSIZE 61, 101](#)
[KD2_PF_HIS_COLL_INTV 63, 101](#)
[KD2_PF_HIS_DB2_STAT 70, 102](#)
[KD2_PF_HIS_DYN_MCLAS 72, 103](#)
[KD2_PF_HIS_DYN_SCLAS 73, 104](#)
[KD2_PF_HIS_DYN_UNIT 74, 106](#)
[KD2_PF_HIS_DYN_VOL 74, 107](#)
[KD2_PF_HIS_GDG_DSNAME 75, 108](#)
[KD2_PF_HIS_GDG_MCLAS 76, 109](#)
[KD2_PF_HIS_GDG_SCLAS 76, 110](#)
[KD2_PF_HIS_GDG_UNIT 77, 111](#)
[KD2_PF_HIS_GDG_VOL 78, 112](#)
[KD2_PF_HIS_IFIREAD 66, 112](#)
[KD2_PF_HIS_LOG1 59, 114](#)
[KD2_PF_HIS_LOG3 116](#)
[KD2_PF_HIS_LOG4 117](#)

Batch parameters (*continued*)

[KD2_PF_HIS_LOG5](#) [118](#)
[KD2_PF_HIS_LOG6](#) [119](#)
[KD2_PF_HIS_LOG7](#) [120](#)
[KD2_PF_HIS_NEQSQL](#) [70](#), [121](#)
[KD2_PF_HIS_POSTPCT](#) [69](#), [122](#)
[KD2_PF_HIS_SEQ_ARC_GDGLIM](#) [79](#), [129](#)
[KD2_PF_HIS_SEQ_UNIT1](#) [72](#), [140](#)
[KD2_PF_HIS_SEQ_UNIT2](#) [141](#)
[KD2_PF_HIS_SEQ_UNIT3](#) [141](#)
[KD2_PF_HIS_SEQ_UNIT4](#) [142](#)
[KD2_PF_HIS_SEQ_UNIT5](#) [143](#)
[KD2_PF_HIS_SEQ_UNIT6](#) [143](#)
[KD2_PF_HIS_SEQ_UNIT7](#) [144](#)
[KD2_PF_HIS_SEQ_VOL2](#) [145](#)
[KD2_PF_HIS_SEQ_VOL3](#) [145](#)
[KD2_PF_HIS_SEQ_VOL4](#) [146](#)
[KD2_PF_HIS_SEQ_VOL5](#) [147](#)
[KD2_PF_HIS_SEQ_VOL6](#) [147](#)
[KD2_PF_HIS_SEQ_VOL7](#) [148](#)
[KD2_PF_HIS_SEQLOG2](#) [124](#)
[KD2_PF_HIS_SEQLOG3](#) [124](#)
[KD2_PF_HIS_SEQLOG4](#) [125](#)
[KD2_PF_HIS_SEQLOG5](#) [126](#)
[KD2_PF_HIS_SEQLOG6](#) [126](#)
[KD2_PF_HIS_SEQLOG7](#) [127](#)
[KD2_PF_HIS_START](#) [71](#), [149](#)
[KD2_PF_HIS_SUBINT](#) [64](#), [151](#)
[KD2_PF_HIS_SUBINT_UNIT](#) [65](#), [152](#)
[KD2_PF_HIS_SUSPCOLL](#) [68](#), [152](#)
[KD2_PF_HIS_VSAM_MCLAS1](#) [58](#), [154](#)
[KD2_PF_HIS_VSAM_MCLAS2](#) [155](#)
[KD2_PF_HIS_VSAM_MCLAS3](#) [156](#)
[KD2_PF_HIS_VSAM_MCLAS4](#) [156](#)
[KD2_PF_HIS_VSAM_MCLAS5](#) [157](#)
[KD2_PF_HIS_VSAM_MCLAS6](#) [158](#)
[KD2_PF_HIS_VSAM_MCLAS7](#) [159](#)
[KD2_PF_HIS_VSAM_SCLAS1](#) [58](#), [159](#)
[KD2_PF_HIS_VSAM_SCLAS2](#) [160](#)
[KD2_PF_HIS_VSAM_SCLAS3](#) [161](#)
[KD2_PF_HIS_VSAM_SCLAS4](#) [162](#)
[KD2_PF_HIS_VSAM_SCLAS5](#) [162](#)
[KD2_PF_HIS_VSAM_SCLAS6](#) [163](#)
[KD2_PF_HIS_VSAM_SCLAS7](#) [164](#)
[KD2_PF_HIS_VSAM_VOL1](#) [60](#), [165](#)
[KD2_PF_HIS_VSAM_VOL2](#) [166](#)
[KD2_PF_HIS_VSAM_VOL3](#) [167](#)
[KD2_PF_HIS_VSAM_VOL4](#) [167](#)
[KD2_PF_HIS_VSAM_VOL5](#) [168](#)
[KD2_PF_HIS_VSAM_VOL6](#) [169](#)
[KD2_PF_HIS_VSAM_VOL7](#) [170](#)
[KD2_PF_HIS_WHEN_AUTHID](#) [61](#), [170](#)
[KD2_PF_HIS_WHEN_CONNID](#) [62](#), [171](#)
[KD2_PF_HIS_WHEN_CORRID](#) [63](#), [172](#)
[KD2_PF_HIS_WHEN_ORIG](#) [67](#), [172](#)
[KD2_PF_HIS_WHEN_PLAN](#) [67](#), [173](#)
[KD2_PF_OA_ECM](#) [85](#)
[KD2_PF_OA_INTV](#) [85](#)
[KD2_PF_OA_START](#) [86](#)
[KD2_PF_OA_THRD](#) [87](#)
[KD2_PF_OA_WAIT](#) [88](#)
[KD2_PF_READA_OPBUFSIZE](#) [221](#)
[KD2_PF_READA_OPBUFTHR](#) [222](#)
[KD2_PF_READA_SPMON](#) [223](#)

Batch parameters (*continued*)

[KD2_PF_SH_D2SHDATA](#) [180](#)
[KD2_PF_SH_D2SHDATI](#) [181](#)
[KD2_PF_SH_D2SHKHST](#) [181](#)
[KD2_PF_SH_D2SHLTHD](#) [182](#)
[KD2_PF_SH_D2SHSPAI](#) [183](#)
[KD2_PF_SH_D2SHSPAR](#) [184](#)
[KD2_PF_SH_D2SHSQLC](#) [184](#)
[KD2_PF_SH_D2SHSQLI](#) [185](#)
[KD2_PF_SH_D2SHSQLT](#) [186](#)
[KD2_PF_SH_D2SHSSZE](#) [186](#)
[KD2_PF_SH_D2SHSTAI](#) [187](#)
[KD2_PF_SH_D2SHSTAT](#) [188](#)
[KD2_PF_SH_D2SHTHDD](#) [189](#)
[KD2_PF_SH_D2SHTHDI](#) [189](#)
[KD2_PF_SH_D2SQCON1](#) [190](#)
[KD2_PF_SH_D2SQCON2](#) [191](#)
[KD2_PF_SH_D2SQCON3](#) [191](#)
[KD2_PF_SH_D2SQCON4](#) [192](#)
[KD2_PF_SH_D2SQCON5](#) [192](#)
[KD2_PF_SH_D2SQCON6](#) [193](#)
[KD2_PF_SH_D2SQCOR1](#) [194](#)
[KD2_PF_SH_D2SQCOR2](#) [194](#)
[KD2_PF_SH_D2SQCOR3](#) [195](#)
[KD2_PF_SH_D2SQCOR4](#) [195](#)
[KD2_PF_SH_D2SQCOR5](#) [196](#)
[KD2_PF_SH_D2SQCOR6](#) [197](#)
[KD2_PF_SH_D2SQPLA1](#) [197](#)
[KD2_PF_SH_D2SQPLA2](#) [198](#)
[KD2_PF_SH_D2SQPLA3](#) [199](#)
[KD2_PF_SH_D2SQPLA4](#) [199](#)
[KD2_PF_SH_D2SQPLA5](#) [200](#)
[KD2_PF_SH_D2SQPLA6](#) [200](#)
[KD2_PF_SH_D2SQPRI1](#) [201](#)
[KD2_PF_SH_D2SQPRI2](#) [202](#)
[KD2_PF_SH_D2SQPRI3](#) [202](#)
[KD2_PF_SH_D2SQPRI4](#) [203](#)
[KD2_PF_SH_D2SQPRI5](#) [203](#)
[KD2_PF_SH_D2SQPRI6](#) [204](#)
[KD2_PF_SQLID](#) [79](#)
[KD2_PF_SQLPA_CF_ANLC](#) [212](#)
[KD2_PF_SQLPA_CF_ANLP](#) [213](#)
[KD2_PF_SQLPA_CF_ENBL](#) [214](#)
[KD2_PF_SQLPA_ENABLE](#) [214](#)
[KD2_PF_SQLPA_STEPDSN](#) [215](#)
[KD2_PF_SQLPA_VERSION](#) [216](#)
[KD2_PF_TRACES_318](#) [217](#)
[KD2_PF_TRACES_400](#) [217](#)
[KD2_PF_TRACES_DB2CMD2](#) [218](#)
[KD2_PF_TRACES_DB2CMD3](#) [219](#)
[KD2_PF_TRACES_DB2CMD4](#) [219](#)
[KD2_PLAN_NAME_OVERRIDE](#) [82](#)

C

[comments](#), [sending](#) [3](#)
[cookie policy](#) [225](#), [227](#)

D

[DB2 Explain](#) [204](#)
[DB2 subsystem](#) [83](#)

G

[GBL_DB2_KD2_CLASSIC_STC 7](#)
[GBL_DSN_DB2_DSNEXT 8](#)
[GBL_DSN_DB2_LOADLIB_V10 8](#)
[GBL_DSN_DB2_LOADLIB_V11 9](#)
[GBL_DSN_DB2_LOADLIB_V12 10](#)
[GBL_DSN_DB2_RUNLIB_V10 11](#)
[GBL_DSN_DB2_RUNLIB_V11 12](#)
[GBL_DSN_DB2_RUNLIB_V12 12](#)

H

[how to 83](#)

K

[KD2_CLASSIC_DB2ID_DEFAULT 13](#)
[KD2_CLASSIC_DB2PM_PLANPKG_OWNER 14](#)
[KD2_CLASSIC_LROWS 16](#)
[KD2_CLASSIC_MVS_SYSID 17](#)
[KD2_CLASSIC_UMAX 18](#)
[KD2_CLASSIC_USER_PROFILE 19](#)
[KD2_CLASSIC_VTAM_APPL_LOGON 19](#)
[KD2_CLASSIC_VTAM_NODE 20](#)
[KD2_OMPE_AUTH_FAIL 21](#)
[KD2_OMPE_AUTODETECT 21](#)
[KD2_OMPE_CCPC_TIMER 22](#)
[KD2_OMPE_CCPC_TRACE 23](#)
[KD2_OMPE_CF_REBUILT 24](#)
[KD2_OMPE_CHECKSYS 25](#)
[KD2_OMPE_CPU_PARALLEL 25](#)
[KD2_OMPE_DB2_EVENT 26](#)
[KD2_OMPE_DB2_EXIT 27](#)
[KD2_OMPE_DB2_USER 28](#)
[KD2_OMPE_DEADLOCK 28](#)
[KD2_OMPE_DSHLQ 29](#)
[KD2_OMPE_DSN_EXTENT 30](#)
[KD2_OMPE_DSP_SIZE 31](#)
[KD2_OMPE_E2E_MON_SPRT 32](#)
[KD2_OMPE_EDMP_FULL 32](#)
[KD2_OMPE_EXTENT_THOLD 33](#)
[KD2_OMPE_GLOBAL_TRACE 34](#)
[KD2_OMPE_GRANT_AGUSER 34](#)
[KD2_OMPE_GRANT_EXUSER 35](#)
[KD2_OMPE_GRANT_PEUSER 35](#)
[KD2_OMPE_GRANT_PWUSER 36](#)
[KD2_OMPE_ISPF_LANGUAGE 36](#)
[KD2_OMPE_LOGSPACE 37](#)
[KD2_OMPE_MAX_SESSIONS 38](#)
[KD2_OMPE_MGMTCLAS 38](#)
[KD2_OMPE_PE_SUPPORT 39](#)
[KD2_OMPE_RUNALLOC 40](#)
[KD2_OMPE_SHARED_PROFILE_LIB 41](#)
[KD2_OMPE_STOCLAS 41](#)
[KD2_OMPE_SUB_D2PADASP 42](#)
[KD2_OMPE_SUB_D2PAGRPN 43](#)
[KD2_OMPE_SUB_D2PARCVT 44](#)
[KD2_OMPE_SUB_D2PASSIT 45](#)
[KD2_OMPE_SUB_D2PATSEC 45](#)
[KD2_OMPE_SUB_D2PAXCFT 46](#)
[KD2_OMPE_SYSAFF 47](#)
[KD2_OMPE_TCPIP_ADDRESS 48](#)

[KD2_OMPE_TCPIP_NAME 49](#)
[KD2_OMPE_THREAD_COMMIT 49](#)
[KD2_OMPE_TIMEOUT 50](#)
[KD2_OMPE_TRACE_LEVEL 51](#)
[KD2_OMPE_UNIT 51](#)
[KD2_OMPE_UR 52](#)
[KD2_OMPE_USE_MODEL 53](#)
[KD2_OMPE_VOLUME 54](#)
[KD2_OMPE_VSAM_DSHLQ 54, 99](#)
[KD2_OMPE_VSAM_MGMTCLAS 55](#)
[KD2_OMPE_VSAM_STOCLAS 56](#)
[KD2_OMPE_VSAM_VOLUME 56](#)
[KD2_PFn ACS_DB2MSGMON 220](#)
[KD2_PFn_AEXCP_D2PYACT 88](#)
[KD2_PFn_AEXCP_D2TPFDSN 89](#)
[KD2_PFn_AEXCP_D2TPFDSP 89](#)
[KD2_PFn_AEXCP_D2TPFFLG 90](#)
[KD2_PFn_AEXCP_D2TPINTV 91](#)
[KD2_PFn_AEXCP_D2TPLDSN 92](#)
[KD2_PFn_AEXCP_D2TPLDSP 92](#)
[KD2_PFn_AEXCP_D2TPLFLG 93](#)
[KD2_PFn_AEXCP_D2TPTDSN 94](#)
[KD2_PFn_AEXCP_D2TPTFMC 95](#)
[KD2_PFn_AEXCP_D2TPTFSC 96](#)
[KD2_PFn_AEXCP_D2TPUID 96](#)
[KD2_PFn_AEXCP_D2TPUXIT 97](#)
[KD2_PFn_AEXCP_D2TPVL 98](#)
[KD2_PFn_DCM_D2SHDCAI 176](#)
[KD2_PFn_DCM_D2SHDCAP 177](#)
[KD2_PFn_DCM_D2SHDCSI 178](#)
[KD2_PFn_DCM_D2SHDCST 179](#)
[KD2_PFn_EX_D2EXACT 204](#)
[KD2_PFn_EX_D2EXDB 205](#)
[KD2_PFn_EX_D2EXOBJ 206](#)
[KD2_PFn_EX_D2EXQMF 210](#)
[KD2_PFn_EX_D2EXQFI 211](#)
[KD2_PFn_HIS_ACCTG_CLAS 100](#)
[KD2_PFn_HIS_BUFSIZE 61, 100](#)
[KD2_PFn_HIS_COLL_INTV 63, 101](#)
[KD2_PFn_HIS_DB2_STAT 70, 102](#)
[KD2_PFn_HIS_DYN_DSNAME 102](#)
[KD2_PFn_HIS_DYN_MCLAS 72, 103](#)
[KD2_PFn_HIS_DYN_PRIMARY 104](#)
[KD2_PFn_HIS_DYN_SCLAS 73, 104](#)
[KD2_PFn_HIS_DYN_SECONDARY 105](#)
[KD2_PFn_HIS_DYN_SQL 105](#)
[KD2_PFn_HIS_DYN_UNIT 73, 106](#)
[KD2_PFn_HIS_DYN_VOLUME 74, 106](#)
[KD2_PFn_HIS_GDG_DSNAME 75, 107](#)
[KD2_PFn_HIS_GDG_LIM 108](#)
[KD2_PFn_HIS_GDG_MCLAS 75, 108](#)
[KD2_PFn_HIS_GDG_PRIMARY 109](#)
[KD2_PFn_HIS_GDG_SCLAS 76, 109](#)
[KD2_PFn_HIS_GDG_SECONDARY 110](#)
[KD2_PFn_HIS_GDG_UNIT 77, 110](#)
[KD2_PFn_HIS_GDG_VOLUME 77, 111](#)
[KD2_PFn_HIS_IFIREAD 65, 112](#)
[KD2_PFn_HIS_LOCK_CNTN 113](#)
[KD2_PFn_HIS_LOCK_SUSP 113](#)
[KD2_PFn_HIS_LOG1 58, 113](#)
[KD2_PFn_HIS_LOG2 114, 115](#)
[KD2_PFn_HIS_LOG3 116](#)
[KD2_PFn_HIS_LOG4 117](#)
[KD2_PFn_HIS_LOG5 118](#)

KD2_PFn_HIS_LOG6 [119](#)
 KD2_PFn_HIS_LOG7 [120](#)
 KD2_PFn_HIS_NEQSQL [69, 121](#)
 KD2_PFn_HIS_POSTPCT [68, 121](#)
 KD2_PFn_HIS_SCAN_SUMM [122](#)
 KD2_PFn_HIS_SEQ_ARC_DS [127](#)
 KD2_PFn_HIS_SEQ_ARC_GDGLIM [78, 128](#)
 KD2_PFn_HIS_SEQ_ARC_MCLAS [129](#)
 KD2_PFn_HIS_SEQ_ARC_SCLAS [129](#)
 KD2_PFn_HIS_SEQ_ARC_TYP [130](#)
 KD2_PFn_HIS_SEQ_ARC_UNIT [131](#)
 KD2_PFn_HIS_SEQ_ARC_VOLUME [131](#)
 KD2_PFn_HIS_SEQ_MCLAS1 [132](#)
 KD2_PFn_HIS_SEQ_MCLAS2 [132](#)
 KD2_PFn_HIS_SEQ_MCLAS3 [133](#)
 KD2_PFn_HIS_SEQ_MCLAS4 [133](#)
 KD2_PFn_HIS_SEQ_MCLAS5 [133](#)
 KD2_PFn_HIS_SEQ_MCLAS6 [134](#)
 KD2_PFn_HIS_SEQ_MCLAS7 [134](#)
 KD2_PFn_HIS_SEQ_PRIMARY_CYL [135](#)
 KD2_PFn_HIS_SEQ_SCLAS1 [135](#)
 KD2_PFn_HIS_SEQ_SCLAS2 [136](#)
 KD2_PFn_HIS_SEQ_SCLAS3 [136](#)
 KD2_PFn_HIS_SEQ_SCLAS4 [137](#)
 KD2_PFn_HIS_SEQ_SCLAS5 [137](#)
 KD2_PFn_HIS_SEQ_SCLAS6 [138](#)
 KD2_PFn_HIS_SEQ_SCLAS7 [138](#)
 KD2_PFn_HIS_SEQ_SECONDARY_CYL [138](#)
 KD2_PFn_HIS_SEQ_TYP [139](#)
 KD2_PFn_HIS_SEQ_UNIT1 [71, 140](#)
 KD2_PFn_HIS_SEQ_UNIT2 [140](#)
 KD2_PFn_HIS_SEQ_UNIT3 [141](#)
 KD2_PFn_HIS_SEQ_UNIT4 [142](#)
 KD2_PFn_HIS_SEQ_UNIT5 [142](#)
 KD2_PFn_HIS_SEQ_UNIT6 [143](#)
 KD2_PFn_HIS_SEQ_UNIT7 [143](#)
 KD2_PFn_HIS_SEQ_VOLUME1 [144](#)
 KD2_PFn_HIS_SEQ_VOLUME2 [144](#)
 KD2_PFn_HIS_SEQ_VOLUME3 [145](#)
 KD2_PFn_HIS_SEQ_VOLUME4 [146](#)
 KD2_PFn_HIS_SEQ_VOLUME5 [146](#)
 KD2_PFn_HIS_SEQ_VOLUME6 [147](#)
 KD2_PFn_HIS_SEQ_VOLUME7 [148](#)
 KD2_PFn_HIS_SEQLOG1 [123](#)
 KD2_PFn_HIS_SEQLOG2 [123](#)
 KD2_PFn_HIS_SEQLOG3 [124](#)
 KD2_PFn_HIS_SEQLOG4 [125](#)
 KD2_PFn_HIS_SEQLOG5 [125](#)
 KD2_PFn_HIS_SEQLOG6 [126](#)
 KD2_PFn_HIS_SEQLOG7 [127](#)
 KD2_PFn_HIS_SORT_SUMM [148](#)
 KD2_PFn_HIS_START [70, 149](#)
 KD2_PFn_HIS_STORE [149](#)
 KD2_PFn_HIS_SUBINT [64, 150](#)
 KD2_PFn_HIS_SUBINT_UNIT [65, 151](#)
 KD2_PFn_HIS_SUBPCOLL [67, 152](#)
 KD2_PFn_HIS_VSAM_MB [153](#)
 KD2_PFn_HIS_VSAM_MCLAS1 [57, 154](#)
 KD2_PFn_HIS_VSAM_MCLAS2 [154](#)
 KD2_PFn_HIS_VSAM_MCLAS3 [155](#)
 KD2_PFn_HIS_VSAM_MCLAS4 [156](#)
 KD2_PFn_HIS_VSAM_MCLAS5 [157](#)
 KD2_PFn_HIS_VSAM_MCLAS6 [157](#)
 KD2_PFn_HIS_VSAM_MCLAS7 [158](#)

KD2_PFn_HIS_VSAM_SCLAS1 [58, 159](#)
 KD2_PFn_HIS_VSAM_SCLAS2 [160](#)
 KD2_PFn_HIS_VSAM_SCLAS3 [160](#)
 KD2_PFn_HIS_VSAM_SCLAS4 [161](#)
 KD2_PFn_HIS_VSAM_SCLAS5 [162](#)
 KD2_PFn_HIS_VSAM_SCLAS6 [163](#)
 KD2_PFn_HIS_VSAM_SCLAS7 [163](#)
 KD2_PFn_HIS_VSAM_SU [164](#)
 KD2_PFn_HIS_VSAM_VOLUME1 [59, 165](#)
 KD2_PFn_HIS_VSAM_VOLUME2 [165](#)
 KD2_PFn_HIS_VSAM_VOLUME3 [166](#)
 KD2_PFn_HIS_VSAM_VOLUME4 [167](#)
 KD2_PFn_HIS_VSAM_VOLUME5 [168](#)
 KD2_PFn_HIS_VSAM_VOLUME6 [168](#)
 KD2_PFn_HIS_VSAM_VOLUME7 [169](#)
 KD2_PFn_HIS_WHEN_AUTHID [60, 170](#)
 KD2_PFn_HIS_WHEN_CONNID [62, 171](#)
 KD2_PFn_HIS_WHEN_CORRID [62, 171](#)
 KD2_PFn_HIS_WHEN_ORIG [66, 172](#)
 KD2_PFn_HIS_WHEN_PLAN [67, 173](#)
 KD2_PFn_OA_ECM [84](#)
 KD2_PFn_OA_INTV [85](#)
 KD2_PFn_OA_START [86](#)
 KD2_PFn_OA_THREAD [86](#)
 KD2_PFn_OA_WAIT [87](#)
 KD2_PFn_READA_OPBUFSIZE [220](#)
 KD2_PFn_READA_OPBUFTHR [221](#)
 KD2_PFn_READA_SPMON [222](#)
 KD2_PFn_SH_D2SHDATA [179](#)
 KD2_PFn_SH_D2SHDATI [180](#)
 KD2_PFn_SH_D2SHKHST [181](#)
 KD2_PFn_SH_D2SHLTHD [182](#)
 KD2_PFn_SH_D2SHSPAI [182](#)
 KD2_PFn_SH_D2SHSPAR [183](#)
 KD2_PFn_SH_D2SHSQLC [184](#)
 KD2_PFn_SH_D2SHSQLI [184](#)
 KD2_PFn_SH_D2SHSQLT [185](#)
 KD2_PFn_SH_D2SHSSZE [186](#)
 KD2_PFn_SH_D2SHSTAI [187](#)
 KD2_PFn_SH_D2SHSTAT [187](#)
 KD2_PFn_SH_D2SHTHDD [188](#)
 KD2_PFn_SH_D2SHTHDI [189](#)
 KD2_PFn_SH_D2SQCON1 [190](#)
 KD2_PFn_SH_D2SQCON2 [190](#)
 KD2_PFn_SH_D2SQCON3 [191](#)
 KD2_PFn_SH_D2SQCON4 [191](#)
 KD2_PFn_SH_D2SQCON5 [192](#)
 KD2_PFn_SH_D2SQCON6 [193](#)
 KD2_PFn_SH_D2SQCOR1 [193](#)
 KD2_PFn_SH_D2SQCOR2 [194](#)
 KD2_PFn_SH_D2SQCOR3 [194](#)
 KD2_PFn_SH_D2SQCOR4 [195](#)
 KD2_PFn_SH_D2SQCOR5 [196](#)
 KD2_PFn_SH_D2SQCOR6 [196](#)
 KD2_PFn_SH_D2SQPLA1 [197](#)
 KD2_PFn_SH_D2SQPLA2 [198](#)
 KD2_PFn_SH_D2SQPLA3 [198](#)
 KD2_PFn_SH_D2SQPLA4 [199](#)
 KD2_PFn_SH_D2SQPLA5 [199](#)
 KD2_PFn_SH_D2SQPLA6 [200](#)
 KD2_PFn_SH_D2SQPRI1 [201](#)
 KD2_PFn_SH_D2SQPRI2 [201](#)
 KD2_PFn_SH_D2SQPRI3 [202](#)
 KD2_PFn_SH_D2SQPRI4 [202](#)

[KD2_PFn_SH_D2SQPRI5](#) [203](#)
[KD2_PFn_SH_D2SQPRI6](#) [204](#)
[KD2_PFn_SQLID](#) [79](#)
[KD2_PFn_SQLPA_CF_ANLC](#) [212](#)
[KD2_PFn_SQLPA_CF_ANLP](#) [212](#)
[KD2_PFn_SQLPA_CF_ENBL](#) [213](#)
[KD2_PFn_SQLPA_ENABLE](#) [214](#)
[KD2_PFn_SQLPA_STEPDSN](#) [215](#)
[KD2_PFn_SQLPA_VERSION](#) [215](#)
[KD2_PFn_THRDHIS_DYN_SQL](#) [173](#)
[KD2_PFn_THRDHIS_LOCK_CNTN](#) [174](#)
[KD2_PFn_THRDHIS_LOCK_SUSP](#) [174](#)
[KD2_PFn_THRDHIS_LOG_NUM](#) [175](#)
[KD2_PFn_THRDHIS_SCAN_SUMM](#) [175](#)
[KD2_PFn_TRACES_318](#) [216](#)
[KD2_PFn_TRACES_400](#) [217](#)
[KD2_PFn_TRACES_DB2CMD2](#) [218](#)
[KD2_PFn_TRACES_DB2CMD3](#) [218](#)
[KD2_PFn_TRACES_DB2CMD4](#) [219](#)
[KD2_PLAN_NAME_OVERRIDE](#) [80](#)

L

legal notices

[cookie policy](#) [225](#), [227](#)
[notices](#) [225](#)
[programming interface information](#) [225](#), [226](#)
[trademarks](#) [225–227](#)

N

[notices](#) [225](#), [226](#)

O

[object analysis](#) [84](#)

P

parameters

[DB2 Explain](#) [204](#)
[DB2 traces](#) [216](#)
[main functions](#) [5](#)
[monitoring features](#) [220](#)
[object analysis](#) [84](#)
[periodic exception processing](#) [88](#)
[profile](#) [83](#)
[snapshot history](#) [176](#)
[SQL Performance Analyzer](#) [212](#)
[thread history](#) [98](#)
[volume analysis](#) [84](#)

PARMGEN parameters

[GBL_DB2_KD2_CLASSIC_STC](#) [8](#)
[GBL_DSN_DB2_DSNEXT](#) [8](#)
[GBL_DSN_DB2_LOADLIB_V10](#) [9](#)
[GBL_DSN_DB2_LOADLIB_V11](#) [10](#)
[GBL_DSN_DB2_LOADLIB_V12](#) [11](#)
[GBL_DSN_DB2_RUNLIB_V10](#) [12](#)
[GBL_DSN_DB2_RUNLIB_V11](#) [12](#)
[GBL_DSN_DB2_RUNLIB_V12](#) [13](#)
[KD2_CLASSIC_DB2ID_DEFAULT](#) [14](#)
[KD2_CLASSIC_DB2PM_PLANPKG_OWNER](#) [16](#)
[KD2_CLASSIC_LROWS](#) [17](#)

PARMGEN parameters (continued)

[KD2_CLASSIC_MVS_SYSID](#) [18](#)
[KD2_CLASSIC_UMAX](#) [19](#)
[KD2_CLASSIC_USER_PROFILE](#) [19](#)
[KD2_CLASSIC_VTAM_APPL_LOGON](#) [20](#)
[KD2_CLASSIC_VTAM_NODE](#) [20](#)
[KD2_OMPE_AUTH_FAIL](#) [21](#)
[KD2_OMPE_AUTODETECT](#) [22](#)
[KD2_OMPE_CCPC_TIMER](#) [23](#)
[KD2_OMPE_CCPC_TRACE](#) [24](#)
[KD2_OMPE_CF_REBUILT](#) [24](#)
[KD2_OMPE_CHECKSYS](#) [25](#)
[KD2_OMPE_CPU_PARALLEL](#) [26](#)
[KD2_OMPE_DB2_EVENT](#) [27](#)
[KD2_OMPE_DB2_EXIT](#) [28](#)
[KD2_OMPE_DB2_USER](#) [28](#)
[KD2_OMPE_DEADLOCK](#) [29](#)
[KD2_OMPE_DSHLQ](#) [30](#)
[KD2_OMPE_DSN_EXTENT](#) [31](#)
[KD2_OMPE_DSP_SIZE](#) [31](#)
[KD2_OMPE_E2E_MON_SPRT](#) [32](#)
[KD2_OMPE_EDMP_FULL](#) [33](#)
[KD2_OMPE_EXTENT_THOLD](#) [34](#)
[KD2_OMPE_GLOBAL_TRACE](#) [34](#)
[KD2_OMPE_GRANT_AGUSER](#) [35](#)
[KD2_OMPE_GRANT_EXUSER](#) [35](#)
[KD2_OMPE_GRANT_PEUSER](#) [36](#)
[KD2_OMPE_GRANT_PWUSER](#) [36](#)
[KD2_OMPE_ISPF_LANGUAGE](#) [37](#)
[KD2_OMPE_LOGSPACE](#) [38](#)
[KD2_OMPE_MAX_SESSIONS](#) [38](#)
[KD2_OMPE_MGMTCLAS](#) [39](#)
[KD2_OMPE_PE_SUPPORT](#) [40](#)
[KD2_OMPE_RUNALLOC](#) [41](#)
[KD2_OMPE_SHARED_PROFILE_LIB](#) [41](#)
[KD2_OMPE_STOCLAS](#) [42](#)
[KD2_OMPE_SUB_D2PADASP](#) [43](#)
[KD2_OMPE_SUB_D2PAGRPN](#) [44](#)
[KD2_OMPE_SUB_D2PARCVT](#) [44](#)
[KD2_OMPE_SUB_D2PASSIT](#) [45](#)
[KD2_OMPE_SUB_D2PATSEC](#) [46](#)
[KD2_OMPE_SUB_D2PAXCFT](#) [47](#)
[KD2_OMPE_SYSAFF](#) [48](#)
[KD2_OMPE_TCPIP_ADDRESS](#) [48](#)
[KD2_OMPE_TCPIP_NAME](#) [49](#)
[KD2_OMPE_THREAD_COMMIT](#) [50](#)
[KD2_OMPE_TIMEOUT](#) [50](#)
[KD2_OMPE_TRACE_LEVEL](#) [51](#)
[KD2_OMPE_UNIT](#) [52](#)
[KD2_OMPE_UR](#) [53](#)
[KD2_OMPE_USE_MODEL](#) [53](#)
[KD2_OMPE_VOLUME](#) [54](#)
[KD2_OMPE_VSAM_DSHLQ](#) [55](#), [99](#)
[KD2_OMPE_VSAM_MGMTCLAS](#) [56](#)
[KD2_OMPE_VSAM_STOCLAS](#) [56](#)
[KD2_OMPE_VSAM_VOLUME](#) [57](#)
[KD2_PFn_ACS_DB2MSGMON](#) [220](#)
[KD2_PFn_AEXCP_D2PYACT](#) [89](#)
[KD2_PFn_AEXCP_D2TPFDSN](#) [89](#)
[KD2_PFn_AEXCP_D2TPFDSP](#) [90](#)
[KD2_PFn_AEXCP_D2TPFLG](#) [91](#)
[KD2_PFn_AEXCP_D2TPINTV](#) [92](#)
[KD2_PFn_AEXCP_D2TPLDSN](#) [92](#)
[KD2_PFn_AEXCP_D2TPLDSP](#) [93](#)

PARMGEN parameters (*continued*)

[KD2_PFn_AEXCP_D2TPLFLG 94](#)
[KD2_PFn_AEXCP_D2TPTDSN 95](#)
[KD2_PFn_AEXCP_D2TPTFMC 96](#)
[KD2_PFn_AEXCP_D2TPTFSC 96](#)
[KD2_PFn_AEXCP_D2TPUID 97](#)
[KD2_PFn_AEXCP_D2TPUXIT 98](#)
[KD2_PFn_AEXCP_D2TPVL 98](#)
[KD2_PFn_DCM_D2SHDCAI 177](#)
[KD2_PFn_DCM_D2SHDCAP 178](#)
[KD2_PFn_DCM_D2SHDCSI 179](#)
[KD2_PFn_DCM_D2SHDCST 179](#)
[KD2_PFn_EX_D2EXACT 205](#)
[KD2_PFn_EX_D2EXDB 206](#)
[KD2_PFn_EX_D2EXOBJ 210](#)
[KD2_PFn_EX_D2EXQMF 211](#)
[KD2_PFn_EX_D2EXQMI 211](#)
[KD2_PFn_HIS_ACCTG_CLAS 100](#)
[KD2_PFn_HIS_BUFSIZE 61, 101](#)
[KD2_PFn_HIS_COLL_INTV 63, 102](#)
[KD2_PFn_HIS_DB2_STAT 70, 102](#)
[KD2_PFn_HIS_DYN_DSNAME 103](#)
[KD2_PFn_HIS_DYN_MCLAS 72, 103](#)
[KD2_PFn_HIS_DYN_PRIMARY 104](#)
[KD2_PFn_HIS_DYN_SCLAS 73, 105](#)
[KD2_PFn_HIS_DYN_SECONDARY 105](#)
[KD2_PFn_HIS_DYN_SQL 106](#)
[KD2_PFn_HIS_DYN_UNIT 74, 106](#)
[KD2_PFn_HIS_DYN_VOLUME 74, 107](#)
[KD2_PFn_HIS_GDG_DSNAME 75, 108](#)
[KD2_PFn_HIS_GDG_LIM 108](#)
[KD2_PFn_HIS_GDG_MCLAS 76, 109](#)
[KD2_PFn_HIS_GDG_PRIMARY 109](#)
[KD2_PFn_HIS_GDG_SCLAS 76, 110](#)
[KD2_PFn_HIS_GDG_SECONDARY 110](#)
[KD2_PFn_HIS_GDG_UNIT 77, 111](#)
[KD2_PFn_HIS_GDG_VOLUME 78, 112](#)
[KD2_PFn_HIS_IFIREAD 66, 112](#)
[KD2_PFn_HIS_LOCK_CNTN 113](#)
[KD2_PFn_HIS_LOCK_SUSP 113](#)
[KD2_PFn_HIS_LOG1 59, 114](#)
[KD2_PFn_HIS_LOG2 115](#)
[KD2_PFn_HIS_LOG3 116](#)
[KD2_PFn_HIS_LOG4 117](#)
[KD2_PFn_HIS_LOG5 118](#)
[KD2_PFn_HIS_LOG6 119](#)
[KD2_PFn_HIS_LOG7 120](#)
[KD2_PFn_HIS_NEQSQL 70, 121](#)
[KD2_PFn_HIS_POSTPCT 69, 122](#)
[KD2_PFn_HIS_SCAN_SUMM 122](#)
[KD2_PFn_HIS_SEQ_ARC_DS 128](#)
[KD2_PFn_HIS_SEQ_ARC_GDGLIM 79, 129](#)
[KD2_PFn_HIS_SEQ_ARC_MCLAS 129](#)
[KD2_PFn_HIS_SEQ_ARC_SCLAS 130](#)
[KD2_PFn_HIS_SEQ_ARC_TYP 130](#)
[KD2_PFn_HIS_SEQ_ARC_UNIT 131](#)
[KD2_PFn_HIS_SEQ_ARC_VOLUME 132](#)
[KD2_PFn_HIS_SEQ_MCLAS1 132](#)
[KD2_PFn_HIS_SEQ_MCLAS2 132](#)
[KD2_PFn_HIS_SEQ_MCLAS3 133](#)
[KD2_PFn_HIS_SEQ_MCLAS4 133](#)
[KD2_PFn_HIS_SEQ_MCLAS5 134](#)
[KD2_PFn_HIS_SEQ_MCLAS6 134](#)
[KD2_PFn_HIS_SEQ_MCLAS7 135](#)

PARMGEN parameters (*continued*)

[KD2_PFn_HIS_SEQ_PRIMARY_CYL 135](#)
[KD2_PFn_HIS_SEQ_SCLAS1 136](#)
[KD2_PFn_HIS_SEQ_SCLAS2 136](#)
[KD2_PFn_HIS_SEQ_SCLAS3 137](#)
[KD2_PFn_HIS_SEQ_SCLAS4 137](#)
[KD2_PFn_HIS_SEQ_SCLAS5 137](#)
[KD2_PFn_HIS_SEQ_SCLAS6 138](#)
[KD2_PFn_HIS_SEQ_SCLAS7 138](#)
[KD2_PFn_HIS_SEQ_SECONDARY_CYL 139](#)
[KD2_PFn_HIS_SEQ_TYP 140](#)
[KD2_PFn_HIS_SEQ_UNIT1 72, 140](#)
[KD2_PFn_HIS_SEQ_UNIT2 141](#)
[KD2_PFn_HIS_SEQ_UNIT3 141](#)
[KD2_PFn_HIS_SEQ_UNIT4 142](#)
[KD2_PFn_HIS_SEQ_UNIT5 143](#)
[KD2_PFn_HIS_SEQ_UNIT6 143](#)
[KD2_PFn_HIS_SEQ_UNIT7 144](#)
[KD2_PFn_HIS_SEQ_VOLUME1 144](#)
[KD2_PFn_HIS_SEQ_VOLUME2 145](#)
[KD2_PFn_HIS_SEQ_VOLUME3 146](#)
[KD2_PFn_HIS_SEQ_VOLUME4 146](#)
[KD2_PFn_HIS_SEQ_VOLUME5 147](#)
[KD2_PFn_HIS_SEQ_VOLUME6 147](#)
[KD2_PFn_HIS_SEQ_VOLUME7 148](#)
[KD2_PFn_HIS_SEQLOG1 123](#)
[KD2_PFn_HIS_SEQLOG2 124](#)
[KD2_PFn_HIS_SEQLOG3 124](#)
[KD2_PFn_HIS_SEQLOG4 125](#)
[KD2_PFn_HIS_SEQLOG5 126](#)
[KD2_PFn_HIS_SEQLOG6 127](#)
[KD2_PFn_HIS_SEQLOG7 127](#)
[KD2_PFn_HIS_SORT_SUMM 148](#)
[KD2_PFn_HIS_START 71, 149](#)
[KD2_PFn_HIS_STORE 150](#)
[KD2_PFn_HIS_SUBINT 64, 151](#)
[KD2_PFn_HIS_SUBINT_UNIT 65, 152](#)
[KD2_PFn_HIS_SUSPCOLL 68, 152](#)
[KD2_PFn_HIS_VSAM_MB 153](#)
[KD2_PFn_HIS_VSAM_MCLAS1 58, 154](#)
[KD2_PFn_HIS_VSAM_MCLAS2 155](#)
[KD2_PFn_HIS_VSAM_MCLAS3 156](#)
[KD2_PFn_HIS_VSAM_MCLAS4 156](#)
[KD2_PFn_HIS_VSAM_MCLAS5 157](#)
[KD2_PFn_HIS_VSAM_MCLAS6 158](#)
[KD2_PFn_HIS_VSAM_MCLAS7 159](#)
[KD2_PFn_HIS_VSAM_SCLAS1 58, 159](#)
[KD2_PFn_HIS_VSAM_SCLAS2 160](#)
[KD2_PFn_HIS_VSAM_SCLAS3 161](#)
[KD2_PFn_HIS_VSAM_SCLAS4 162](#)
[KD2_PFn_HIS_VSAM_SCLAS5 162](#)
[KD2_PFn_HIS_VSAM_SCLAS6 163](#)
[KD2_PFn_HIS_VSAM_SCLAS7 164](#)
[KD2_PFn_HIS_VSAM_SU 165](#)
[KD2_PFn_HIS_VSAM_VOLUME1 60, 165](#)
[KD2_PFn_HIS_VSAM_VOLUME2 166](#)
[KD2_PFn_HIS_VSAM_VOLUME3 167](#)
[KD2_PFn_HIS_VSAM_VOLUME4 167](#)
[KD2_PFn_HIS_VSAM_VOLUME5 168](#)
[KD2_PFn_HIS_VSAM_VOLUME6 169](#)
[KD2_PFn_HIS_VSAM_VOLUME7 170](#)
[KD2_PFn_HIS_WHEN_AUTHID 61, 170](#)
[KD2_PFn_HIS_WHEN_CONNID 62, 171](#)
[KD2_PFn_HIS_WHEN_CORRID 63, 172](#)

PARMGEN parameters (*continued*)

[KD2_PFn_HIS_WHEN_ORIG 67, 172](#)
[KD2_PFn_HIS_WHEN_PLAN 67, 173](#)
[KD2_PFn_OA_ECM 85](#)
[KD2_PFn_OA_INTV 85](#)
[KD2_PFn_OA_START 86](#)
[KD2_PFn_OA_THREAD 87](#)
[KD2_PFn_OA_WAIT 88](#)
[KD2_PFn_READA_OPBUFSIZE 221](#)
[KD2_PFn_READA_OPBUFTHR 222](#)
[KD2_PFn_READA_SPMON 223](#)
[KD2_PFn_SH_D2SHDATA 180](#)
[KD2_PFn_SH_D2SHDATI 181](#)
[KD2_PFn_SH_D2SHKHST 181](#)
[KD2_PFn_SH_D2SHLTHD 182](#)
[KD2_PFn_SH_D2SHSPAI 183](#)
[KD2_PFn_SH_D2SHSPAR 184](#)
[KD2_PFn_SH_D2SHSQLC 184](#)
[KD2_PFn_SH_D2SHSQLI 185](#)
[KD2_PFn_SH_D2SHSQLT 186](#)
[KD2_PFn_SH_D2SHSSZE 186](#)
[KD2_PFn_SH_D2SHSTAI 187](#)
[KD2_PFn_SH_D2SHSTAT 188](#)
[KD2_PFn_SH_D2SHTHDD 189](#)
[KD2_PFn_SH_D2SHTHDI 189](#)
[KD2_PFn_SH_D2SQCON1 190](#)
[KD2_PFn_SH_D2SQCON2 191](#)
[KD2_PFn_SH_D2SQCON3 191](#)
[KD2_PFn_SH_D2SQCON4 192](#)
[KD2_PFn_SH_D2SQCON5 192](#)
[KD2_PFn_SH_D2SQCON6 193](#)
[KD2_PFn_SH_D2SQCOR1 194](#)
[KD2_PFn_SH_D2SQCOR2 194](#)
[KD2_PFn_SH_D2SQCOR3 195](#)
[KD2_PFn_SH_D2SQCOR4 196](#)
[KD2_PFn_SH_D2SQCOR5 196](#)
[KD2_PFn_SH_D2SQCOR6 197](#)
[KD2_PFn_SH_D2SQPLA1 197](#)
[KD2_PFn_SH_D2SQPLA2 198](#)
[KD2_PFn_SH_D2SQPLA3 199](#)
[KD2_PFn_SH_D2SQPLA4 199](#)
[KD2_PFn_SH_D2SQPLA5 200](#)
[KD2_PFn_SH_D2SQPLA6 200](#)
[KD2_PFn_SH_D2SQPRI1 201](#)
[KD2_PFn_SH_D2SQPRI2 202](#)
[KD2_PFn_SH_D2SQPRI3 202](#)
[KD2_PFn_SH_D2SQPRI4 203](#)
[KD2_PFn_SH_D2SQPRI5 204](#)
[KD2_PFn_SH_D2SQPRI6 204](#)
[KD2_PFn_SQLID 80](#)
[KD2_PFn_SQLPA_CF_ANLC 212](#)
[KD2_PFn_SQLPA_CF_ANLP 213](#)
[KD2_PFn_SQLPA_CF_ENBL 214](#)
[KD2_PFn_SQLPA_ENABLE 214](#)
[KD2_PFn_SQLPA_STEPDSN 215](#)
[KD2_PFn_SQLPA_VERSION 216](#)
[KD2_PFn_THRDHIS_DYN_SQL 174](#)
[KD2_PFn_THRDHIS_LOCK_CNTN 174](#)
[KD2_PFn_THRDHIS_LOCK_SUSP 174](#)
[KD2_PFn_THRDHIS_LOG_NUM 175](#)
[KD2_PFn_THRDHIS_SCAN_SUMM 175](#)
[KD2_PFn_THRDHIS_SORT_SUMM 176](#)
[KD2_PFn_TRACES_318 217](#)
[KD2_PFn_TRACES_400 217](#)

PARMGEN parameters (*continued*)

[KD2_PFn_TRACES_DB2CMD2 218](#)
[KD2_PFn_TRACES_DB2CMD3 219](#)
[KD2_PFn_TRACES_DB2CMD4 219](#)
[KD2_PLAN_NAME_OVERRIDE 82](#)
periodic exception processing [88](#)
profile [83](#)
programming interface information [225, 226](#)

S

sending comments [3](#)
service [2](#)
snapshot history [176](#)
SQL Performance Analyzer [212](#)
support home website [2](#)

T

thread history [98](#)
trademarks [225–227](#)

U

updates [2](#)

V

volume analysis [84](#)



Product Number: 5655-W37

SH12-7073

